













Manual Planning in the Transportation Cockpit




Explanation	Screenshot
i The purpose of this demonstration is to show how a transportation planner can create freight orders interactively. Choose <i>Next</i> to continue.	
1. The demonstration starts by selecting the freight units that should be planned in the Order Integration - Worklist. Click on the checkbox highlighted to select all freight units from the worklist.	
2. Transportation planning can be done automatically in the background or interactively in the Transportation Cockpit. Choose <i>Transportation Cockpit</i> to start interactive transportation planning.	



Explanation	Screenshot
3. How planning is done and how the planning relevant information is displayed can be configured. The planning profile defines how planning is done (e.g. which resources are available, how to select the best carrier) and the page layout defines how this information is displayed on the screen. When entering the transportation cockpit a combination of planning profile and page layout is selected. Choose <i>Continue</i> to open the transportation cockpit.	 The screenshot shows the 'Transportation Cockpit: Profile and Layout' configuration screen. It features a 'Profile and Layout Sets (3)' table with columns for Description, Note, Freight Unit Selection, Transportation Selection, Consignment Selection, Freight Order Selection, Freight Booking Selection, Capacity Settings, Incomplete Settings, Planning Profile, Page Layout for Transportation Cockpit, Default Set, Unplanned Requirements, and Job Status. Three sets are listed: PLAN_S4TM1 (TCLAYOUT_SIMPLE), PLAN_S4TM1 (TCLAYOUT_VISUAL), and S4TM2-PLA (TCLAYOUT_SIMPLE). Below the table is the 'Start Screen Settings' section with a 'Default Start Screen' dropdown and a 'Hide Screen' checkbox. At the bottom right is a 'Continue' button with a yellow arrow and the text 'Planning as Background Job'.
4. The transportation cockpit lists the freight units (loading location, unloading location, pickup date, delivery date, weight, volume, ...) that need to be planned as well as available trucks (capacities). Depending on the planning scope, the transportation cockpit	 The screenshot shows the 'Transportation Cockpit: TCLAYOUT_SIM' screen. It displays three main sections: 'Freight Unit Stages (3)', 'Road Freight Orders (0)', and 'Trucks (3)'. The 'Freight Unit Stages' table lists items 5109, 5110, and 5111 with details on stage, load/unload, dates, and weights. The 'Trucks' table lists resources TM2FTL-00, TM2LTL-00, and TM2POOL-00. The 'Road Freight Orders' section is currently empty. At the bottom, there are tabs for 'Overview', 'Stages', 'Carrier Ranking', and 'Charges', with a 'Details' tab selected showing a table with columns for Activity, Activity Description, Maxim. Utilization, Document, Load Plan Status, Load Status, Unload Plan Status, Unload Status, Handling Status, and Handling/Transmission Status. A 'Save' button is located at the bottom right.



Explanation	Screenshot
may list container types, vessels or schedules instead. In order to assign the selected freight units to the truck resource TM2FTL-00 select the truck resource highlighted.	
5. The <i>Assign Selected Items</i> button allows you to assign the selected freight units to the selected truck resource (Of course, using drag and drop would also work for this purpose).	
6. The result of the assignment of freight units to a truck resource is a freight order. The system displays the source and destination location of the freight order as well as departure and arrival time, utilization, remaining capacity and others. Choose Save to save the planning result.	

Explanation	Screenshot
7. Choose Actions - Details to explore further the details of the planning result.	
8. You can expand any screen element to full screen in order to analyze the data displayed there in more detail. Expand the Overview of freight order 200000107.	
9. The freight order is displayed in a hierarchical view showing the individual stops of the freight order. Choose Expand All to check what is planned at each stop location.	


Explanation	Screenshot
10. The freight order loads three freight units at the shipping point SP_1010 in Hamburg. Afterwards the freight order continues to Dortmund, Bochum, and Essen and unloads the freight unit for the respective locations there. In the end the truck is empty again. If you prefer a more visual representation of the data you can dynamically switch the transportation cockpit page layout. Choose the page layout <i>TCLAYOUT_VISUAL</i>	
11. Expand the Gantt Chart view of the transportation cockpit.	

Explanation	Screenshot
The Gantt Chart view offers a graphical view on freight units, freight orders, trucks and their utilization (from a time and capacity perspective). Choose <i>Next</i> to explore the Gantt Chart in more detail.	 The screenshot shows the SAP Transportation Cockpit interface with the Gantt Chart view selected. The left pane displays 'Documents and Resources' with a table showing a document '200000107' with status 'Planned' and source location 'SP_1010'. The right pane shows a Gantt chart for 'Friday, Sep 15, 23' from 18:00 to 01:00, with a green bar representing the document's duration.
12. Switch the display to <i>Freight Units and Freight Orders</i>.	 The screenshot shows the same SAP Transportation Cockpit interface, but the 'Freight Units and Freight Orders' menu item is highlighted in the left pane. The Gantt chart on the right remains the same.
13. In the upper half of the screen, you can see the freight units. All of them are loaded at the same time at the shipping point SP_1010 in Hamburg and delivered one after each other. At this level, the freight order view shows the freight order bar from the beginning of first loading to end of last unloading.	 The screenshot shows the SAP Transportation Cockpit interface with the 'Freight Units and Freight Orders' view selected. The left pane displays a table with freight units '5109', '5110', and '5111', all with status 'Planned' and source location 'SP_1010'. The right pane shows a Gantt chart for 'Friday, Sep 15, 23' from 18:00 to 01:00, with multiple green bars representing the duration of each freight unit.

Explanation	Screenshot
Choose <i>Utilization</i> to check the truck utilization.	
The utilization of the truck is shown below the freight order bar. You can see that the truck is loaded to roughly 72% at the beginning of the freight order and the truck utilization is reduced on any of the subsequent delivery stops. Choose <i>Next</i> to continue with the demonstration.	
You can also toggle to an activity based view. In the activity based view, the different activities in the transportation process are highlighted in different colors. Loading is shown in blue, travelling is shown in green and unloading activities are shown in orange. (Of course, colors can be adapted in customizing. The Gantt Chart view also support interactive	

Explanation	Screenshot
planning like drag and drop.) Choose <i>Next</i> to continue with the demonstration.	
14. Another graphical representation of transportation plans makes use of maps. Choose page layout <i>LAYOUT-00</i> (in the system-based exercise you can also choose your user-specific layout <i>LAYOUT-##</i>) to switch to a map based view.	
15. You can choose which information (freight units, resources, freight orders) should be displayed in the map. If you have selected the relevant objects choose <i>Clear Map and Add Selected Entries</i> to update the map with relevant information.	

Explanation	Screenshot
16. Expand the Map view of the transportation cockpit to full screen.	
 In the map you can also display all planning relevant data. The map display is highly customizable. You cannot only choose colors, but also icons and how you want the information to be displayed (arrows, geo-route). Choose Next to continue with the demonstration.	

Explanation	Screenshot
17. Choose <i>Show Detailed Route</i> to switch between arrow-based and geo-route-based representation of the freight order.	
 Similar to the Gantt Chart view also the Map view allows interactive planning via drag and drop. Choose <i>Next</i> to conclude the demonstration.	