USER ACCEPTANCE TESTING (CASHIER)

Project Name	FETCH: Inventory Management System with Predictive Analytics for Risha Pet Supplies		
Testing Start			
Date/Time		Passed (Result is same as expected)	
Testing End		Failed (Actual result is NOT same as expected result)	
Name/s:		In Progress (Test is still in progress or not yet done)	
		Open (Not yet tested)	

Module	TESTCASE	T.S ID	DESCRIPTION	EXPECTED RESULT	ACTUAL RESULT	COMMENT	STATUS
CASHIER							
LOGIN							
	Completeness Check						
		1	Check if a valid sign in works Enter the username and the password, then click Sign in	The user is signed in and taken to the home page of the account			
		2	Check if Username is empty Leave Username empty, then click Sign in	A tooltip "Please fill out this field." is displayed on Username			
		3	Check if Password is empty Leave Password empty, then click Sign in	A tooltip "Please fill out this field." is displayed on Password			
		4	Check if the reset username or email is empty Type the username, click "Forgot your password?", clear the Username or email box, then click Ask for a reset	A tooltip "Please fill out this field." is displayed			
		5	Check if New password is empty Open a reset link, leave New password empty, then click Save new password	A tooltip "Please fill out this field." is displayed			
		6	Check if a username is needed for a reset Leave Username empty, then click "Forgot your password?"	A message "Enter your username first." is displayed and the reset box does not open			
	Format Check						
		1	Check if a password with every kind of character is accepted Open a reset link, enter a new password with an uppercase letter, a lowercase letter, a number and a special character, then click Save new password	A message "Password has been reset. You can now sign in. Redirecting to sign in..." is displayed			

Module	TESTCASE	T.S ID	DESCRIPTION	EXPECTED RESULT	ACTUAL RESULT	COMMENT	STATUS
		2	Check if the password has no uppercase letter Enter a new password without an uppercase letter	A message "Password must contain at least one uppercase letter (A–Z)" is displayed			
		3	Check if the password has no lowercase letter Enter a new password without a lowercase letter	A message "Password must contain at least one lowercase letter (a–z)" is displayed			
		4	Check if the password has no number Enter a new password without a number	A message "Password must contain at least one number (0–9)" is displayed			
		5	Check if the password has no special character Enter a new password without a special character	A message "Password must contain at least one special character (e.g. !@#$%)" is displayed			
	Range Check						
		1	Check if a password of 6 or more characters is saved Enter a new password of 6 characters or more that follows the rules, then click Save new password	The password is saved and the user is taken to the Sign in page			
		2	Check if the password is shorter than 6 characters Enter a new password with fewer than 6 characters	A message "Password must be at least 6 characters long" is displayed			
		3	Check if a 6th wrong sign-in is blocked Enter a wrong password 5 times within 15 minutes, then try a 6th time	A message "Too many login attempts. Try again in (seconds)s." is displayed and sign-in is refused			
	Consistency Check						
		1	Check if the Administrator opens the Dashboard Sign in as Administrator	The Dashboard opens: the administrator's home page, with the shop's figures			
		2	Check if the Cashier opens the Point of Sale Sign in as Cashier	The Point of Sale opens, not the Dashboard, with "Cashier: (name)" of the cashier who signed in			
		3	Check if the Supplier opens the Supplier Portal Sign in as Supplier	The Supplier Portal opens with that supplier's own orders and products			
		4	Check if the two passwords do not match Open a reset link, enter a new password and a different password in Confirm password, then click Save new password	A message "Passwords do not match." is displayed and the password is not changed			
	Database Check						
		1	Check if a saved account can sign in Enter a username and password that are saved in the system, then click Sign in	The user is signed in			
		2	Check if "Keep me signed in" keeps the session Tick "Keep me signed in", sign in, close the browser and open FETCH again	The user is still signed in			
		3	Check if the password is wrong	A message "Invalid username or password" is			

Module	TESTCASE	T.S ID	DESCRIPTION	EXPECTED RESULT	ACTUAL RESULT	COMMENT	STATUS
			Enter a username with a wrong password, then click Sign in	displayed			
		4	Check if the email is not yet confirmed Sign in with an account whose email is not yet confirmed	A message "Please confirm your email address first. Check (email) for the confirmation link." is displayed with a "Resend it" link			
		5	Check if the account is deactivated Sign in with an account that was deactivated	A message "Invalid username or password" is displayed and the account cannot sign in			
		6	Check if the reset link has expired or was used Open a reset link that has expired or was already used	A message "This reset link is invalid or has expired. Please request a new one." is displayed			
NAVIGATION (SIDEBAR AND TOP BAR)							
	Consistency Check						
		1	Check if a cashier can open Inventory Sign in as Cashier, then type the address of the Inventory page (inventory.html)	The page does not open: the cashier is returned to the Point of Sale			
SETTINGS							
	Completeness Check						
		1	Check if a complete profile is saved In Profile, fill in Full name and Email, then click Save changes	A message "Profile updated" is displayed			
		2	Check if Full name is empty In Profile, clear Full name, then click Save changes	A message "Please enter your full name" is displayed			
		3	Check if Current password is empty In Password, leave Current password empty, then click Update password	A message "Enter current password" is displayed			
		4	Check if New password is empty In Password, leave New password empty, then click Update password	A message "Enter new password" is displayed			
		5	Check if Confirm new password is empty In Password, leave Confirm new password empty, then click Update password	A message "Confirm new password" is displayed			
	Format Check						
		1	Check if a correct email is saved In Profile, enter an email with @, then click Save changes	The profile is saved			
		2	Check if the email has no @ In Profile, enter an email without @, then click Save changes	A message "Please enter a valid email address" is displayed			
		3	Check if the new password is too weak	A message "Password too weak" is displayed			

Module	TESTCASE	T.S ID	DESCRIPTION	EXPECTED RESULT	ACTUAL RESULT	COMMENT	STATUS
			In Password, enter a new password without a number or special character	with the missing rule			
		4	Check if the photo is not an image In Profile, upload a file that is not an image as the photo	A message "Please choose an image file" is displayed (a damaged picture shows "That image could not be loaded")			
	Consistency Check						
		1	Check if Session shows the signed-in user Click the Session tab	The full name, role and account status of the signed-in user are displayed (the Cashier role reads "Staff")			
		2	Check if Profile shows the signed-in user Click the Profile tab	The full name and email of the signed-in user are displayed			
		3	Check if the two passwords do not match In Password, enter a different password in Confirm new password	A message "Passwords do not match" is displayed			
	Database Check						
		1	Check if a new email is saved In Profile, enter an email no other account uses, then click Save changes	The profile is saved			
		2	Check if the password is changed In Password, enter the current password and the same new password twice, then click Update password	A message "Password changed" is displayed			
		3	Check if the current password is wrong In Password, enter a wrong current password, then click Update password	A message "Password not changed" is displayed with "Current password is incorrect"			
		4	Check if the email is already used In Profile, enter an email another account uses	A message "That email is already used by another account" is displayed			
POINT OF SALE (CASHIER)							
	Completeness Check						
		1	Check if the starting cash is saved On the first sign-in of the day, enter 500 as the Starting cash, then click Save starting cash	A message "Starting cash saved: ₱500.00" is displayed			
		2	Check if Starting cash is empty Leave Starting cash empty, then click Save starting cash	A message "Enter the cash in the drawer, or 0 if it is empty" is displayed			
		3	Check if the cart is empty Click Charge with an empty cart	A message "Cart is empty" is displayed			
		4	Check if Cash received is empty Add an item, leave Cash received empty, then click	A message "Enter the cash amount received" is displayed			

Module	TESTCASE	T.S ID	DESCRIPTION	EXPECTED RESULT	ACTUAL RESULT	COMMENT	STATUS
			Charge				
		5	Check if the cash amount is empty Click Cash in / out, leave Amount empty, then click Record cash taken out	A message "Enter the amount" is displayed			
		6	Check if the reason for cash taken out is empty Choose Taken out, enter an amount and leave "Who took it, and what for" empty	A message "Say who took the cash and what for" is displayed			
		7	Check if the cash counted is empty Click End of day, leave the cash counted empty, then click Save count and close drawer	A message "Enter the cash counted in the drawer" is displayed			
		8	Check if the void reason is empty In My sales today, click Ask for void and leave the reason empty	A message "Say briefly what went wrong" is displayed			
	Format Check						
		1	Check if numbers in cash and discount are worked out Type numbers in Cash received and Discount	The change and the total are worked out			
		2	Check if letters can be typed in Cash received Type letters in Cash received	The letters are not typed: the field takes numbers only			
		3	Check if letters can be typed in Discount Type letters in Discount	The letters are not typed: the field takes numbers only			
	Range Check						
		1	Check if enough cash is received Enter Cash received equal to or more than the total, then click Charge	The Confirm cash sale window shows the change			
		2	Check if the quantity is more than the stock Change an item's quantity in the cart to more than its "(n) left"	A message "Only (n) in stock" is displayed and the quantity is set to the (n) in stock			
		3	Check if the cash received is less than the total Enter less Cash received than the total, then click Charge	A message "Insufficient cash — customer gave less than the total" is displayed			
		4	Check if the discount is above the limit Enter a discount above the limit, for example 50	A message "The largest discount allowed is (limit)%" is displayed and the discount is lowered to the limit			
		5	Check if an expired product is scanned Scan a product whose expiration date has passed	A message "(product) has expired and cannot be sold" is displayed			
		6	Check if a sold-out product is scanned Scan a product with no stock	A message "(product) is sold out" is displayed			
		7	Check if more cash is taken out than the drawer	A message "That is more cash than the drawer			

Module	TESTCASE	T.S ID	DESCRIPTION	EXPECTED RESULT	ACTUAL RESULT	COMMENT	STATUS
			holds Take out more cash than the drawer holds	should hold." is displayed			
	Consistency Check						
		1	Check if the product card matches Inventory Look at a product card	Its price and "(n) left" are the same as the product's Unit price and stock in Inventory			
		2	Check if a category shows only its products Click a category button	Only the products of that category are shown			
		3	Check if the search shows only matching products Type a product name in the search box	Only the matching products are shown			
		4	Check if the card updates by itself Change a product's stock in Inventory while the till is open, then wait 10 seconds	The product's card shows the new "(n) left" without reloading the page			
		5	Check if the subtotal and total add up Add two items and a discount	The subtotal is the sum of the lines, and the total is the subtotal less the discount			
		6	Check if a sale lowers the stock Complete a sale of 2 of a product, then look at its card and at Inventory	The card's "(n) left" has gone down by 2, and Inventory shows the same new stock			
		7	Check if the receipt matches the sale Look at the receipt after Complete sale	The items, quantities, discount, total, cash received and change are the same as in the Confirm cash sale window			
		8	Check if the sale matches in Sales Sign in as Administrator and open the same sale in Sales	It shows the same items, total and cashier as the receipt			
		9	Check if My sales today shows only this cashier's sales Click My sales today	Only this cashier's sales of today are listed			
		10	Check if the cash in and out totals add up Click Cash in / out	The totals line reads "Put in ₱(amount) · Taken out ₱(amount)" for this drawer today			
		11	Check if the expected cash adds up Click End of day, type the counted cash, then save the count	The expected cash is not shown before saving (a blind count); after saving it equals starting cash + cash sales + cash put in − cash taken out			
		12	Check if "Can't be sold" lists only those products Click "Can't be sold"	Only expired and sold-out products are listed, each marked "Expired (date)" or "None left"			
		13	Check if an unsellable product is among the cards Look for an expired or sold-out product among the product cards	It is not among the cards; it is listed under "Can't be sold"			
		14	Check if a deleted product leaves the till Delete a product in Inventory while the till is open, then wait 10 seconds	The product's card disappears from the till			

Module	TESTCASE	T.S ID	DESCRIPTION	EXPECTED RESULT	ACTUAL RESULT	COMMENT	STATUS
		15	Check if another cashier's sales are listed Click My sales today after another cashier has made sales	Only your own sales are listed, not the other cashier's			
		16	Check if a voided sale is left out of the expected cash Void one of today's sales (administrator), then click End of day at the till	The voided sale is not counted in the expected cash			
	Database Check						
		1	Check if a barcode on record adds the product Scan the barcode of a product on record	The product is added to the cart			
		2	Check if a sale is completed Add items, enter Cash received, click Charge, then click Complete sale	A message "Sale completed! Change: ₱(amount)" is displayed, the stock goes down and the receipt is shown			
		3	Check if cash taken out is recorded Click Cash in / out, choose Taken out, enter the amount and reason, click Record cash taken out, then Record it	A message "Recorded" is displayed and the expected cash goes down by that amount			
		4	Check if the end-of-day count is saved Click End of day, enter the cash counted, then click Save count and close drawer	"Balanced" with a tick, "Over by ₱(amount)" or "Short by ₱(amount)" is shown and the count is saved			
		5	Check if the barcode is not on record Scan or type a barcode that is not on record	A message "No product found for "(barcode)"" is displayed			
		6	Check if a void can be asked for twice Look at a sale that already has a void request in My sales today	The Ask for void button is not shown			
		7	Check if cash can be recorded after the count After the count is saved, click Cash in / out	The window says "Today's cash count is already recorded, so nothing more can be added for today."			
		8	Check if Complete sale is clicked twice Click Complete sale twice quickly	Only one sale is recorded and the stock goes down once			
		9	Check if a sale can be made after the count After the count is saved, click a product card	A message "Your drawer is closed for today" is displayed			