
PresentationDemo Operation Guide

v1.0 2016/03/10

Index

Architecture	3
Access to DemoApplication	4
Screen List	5
Players/TimerOperation Settings	6
DeviceConnectSettings	7
SlideShareSetting And Others	8
How to get parameters of SlideShare	9
slideSuffixSetting	10
About operations of presentation	11

Architecture



Access To DemoApplication

Locate DemoApplication sources(under demoSite folder) to any host.

(In this document, locate those files to local server(192.168.1.199:8080) on Android device by using the Manager's WEB server

function.)

DemoApplication



This app can handle SlideShare parameters in URL.

http://192.168.1.199:8080/#/?userName=KeiichiroFujii&slideName=vdc-5th-ntt

External Sites

🔟 40 40 🔅 🦁 🐨 🗓 🐞 🐞 🕻 🕩 🗸 🗓 🖸 16:24

Slides

デバイスコネクトWebAPIによる

vdc-5th-ntt

VUZIX

192.168.1.199:8080

http://192.168.1.199:8080/list.html


Sample HTML for an access from externals. (It is needs rewriting HostName and Port)

http://192.168.1.199:8080/index.html


This app operates by referencing parameters in cookie If it is opened without the parameters. (Defaults is, userName: KeiichiroFujii, slideName: vdc-5th-ntt)

Screen List

Top Screen Setting Screen




Players/TimerOperation Settings



This dialog will appear if connection with Manager is failed

DeviceConnectSettings

It is possible to check connection with Manager(availability) and set HostName.



The version number will appear if Manager is operating.



Dialogs will appear if connection checking is failed.



Android



iOS



SlideShareSettings And Others



It is possible to set parameters of SlideShare.

If this screen is closed, requests to SlideShare again.


"clear cookie" clear the all setting to defaults.

How to get parameters of SlideShare

1 Access to the SlideShare by PC's browser



Access to the target page, and extract parameters in the URL. Set the parameters to the demo app.




This case,
UserName is "KeiichiroFujii"
SlideName is "vdc-5th-ntt"


slideSuffixSetting

There is a case that the slides cannot be loaded even if correct parameters is set. In that case, try to set slideSuffix.





Examples of slideSuffix the required slide (t_wada, devlove2012-twada-tdd)



For getting slideSuffix, Try right-click on the slide image in Slideshare and select "Copy an address of the image". http:// image.slidesharecdn.com/devlove2012twadatdd-121217020107-phpapp01/95/-1 -638.jpg?cb=1355709811 "-638.jpg" in the URL is slideSuffix. Set the value to the demo app setting screen.

Of course, the value can be included into the demo app's URL. http://<HostName>/#/?userName=t_wada&slideName=devlove2012-twada-tdd&slideSuffix=-638.jpg

About operations of presentation



1 Push "Start"

The slide page is set to 1.

Send the slide url to each player.

Load all timer settings, and set the specified operation that will invoke after a specified time. If the time is set at 0 minutes 0 seconds after, the operation invoke soon.

2 In presentation

Send the slide url to each player when an user switch a slide by "Prev", "Next", "operate slider" and "operate flick".

When the specified time passed, specified operation is invoke.

3 Push "End"

Send request of disappearing slide image to each player.

All timer is canceled.