


JJ Hanekom Week 9 packet tracer practical

Topology (before any steps/tasks)



Task 89

```
Switch>enable
Switch#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Switch(config)#vtp domain CAMPUS
Changing VTP domain name from NULL to CAMPUS
Switch(config)#%SW_VLAN-6-VTP_DOMAIN_NAME_CHG: VTP domain name changed to
CAMPUS.

Switch(config)#vtp mode server
Device mode already VTP SERVER.
Switch(config)#vtp password CampusVTP
Setting device VLAN database password to CampusVTP
Switch(config)#vtp version 2
Switch(config)#
Switch(config)#hostname SW1
SW1(config)#
```

```

Switch>enable
Switch#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Switch(config)#hostname SW2
SW2(config)#
SW2(config)#vtp domain CAMPUS
Changing VTP domain name from NULL to CAMPUS
SW2(config)#%SW_VLAN-6-VTP_DOMAIN_NAME_CHG: VTP domain name changed to CAMPUS.

SW2(config)#vtp mode client
Setting device to VTP CLIENT mode.
SW2(config)#vtp password CampusVTP
Setting device VLAN database password to CampusVTP
SW2(config)#

```

```

Switch>enable
Switch#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Switch(config)#hostname SW3
SW3(config)#
SW3(config)#vtp domain CAMPUS
Changing VTP domain name from NULL to CAMPUS
SW3(config)#%SW_VLAN-6-VTP_DOMAIN_NAME_CHG: VTP domain name changed to CAMPUS.

SW3(config)#vtp mode client
Setting device to VTP CLIENT mode.
SW3(config)#vtp password CampusVTP
Setting device VLAN database password to CampusVTP
SW3(config)#

```

Task 90:

```

SW2(config)#vlan 10
SW2(config-vlan)#name ENG
SW2(config-vlan)#exit
SW2(config)#vlan 20
SW2(config-vlan)#name SALES
SW2(config-vlan)#exit
SW2(config)#

```

```

SW1(config)#int fa0/2
SW1(config-if)#switchport mode access
SW1(config-if)#switchport access vlan 10
SW1(config-if)#exit
SW1(config)#int fa0/3
SW1(config-if)#switchport mode access
SW1(config-if)#switchport access vlan 10
SW1(config-if)#exit
SW1(config)#int fa0/4
SW1(config-if)#switchport mode access
SW1(config-if)#switchport access vlan 20
SW1(config-if)#exit
SW1(config)#int fa0/3
SW1(config-if)#switchport access vlan 20
SW1(config-if)#exit
SW1(config)#int fa0/1
SW1(config-if)#switchport access vlan 10

```

```

SW3#conf t
Enter configuration commands, one per line. End with CNTL/Z.
SW3(config)#int fa0/1
SW3(config-if)#switchport mode trunk
SW3(config-if)#switchport mode access
SW3(config-if)#exit
SW3(config)#int fa0/2
SW3(config-if)#switchport mode access
SW3(config-if)#exit
SW3(config)#int fa0/3
SW3(config-if)#switchport mode access
SW3(config-if)#switchport access vlan 10
SW3(config-if)#exit
SW3(config)#int fa0/1
SW3(config-if)#switchport access vlan 20
SW3(config-if)#exit
SW3(config)#int fa0/2
SW3(config-if)#switchport access vlan 20
SW3(config-if)#

```

Task 91:

```

SW1(config-if)#
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthet
to down

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthet
to up
switchport trunk allowed vlan10,20
^
% Invalid input detected at '^' marker.

SW1(config-if)#
SW1(config-if)#switchport trunk allowed vlan 10,20
SW1(config-if)#

SW2(config)#interface fa0/1
SW2(config-if)#switchport mode trunk
Command rejected: An interface whose trunk encapsulation :
configured to "trunk" mode.
SW2(config-if)#switchport trunk encapsulation dot1q
SW2(config-if)#switchport mode trunk
SW2(config-if)#switchport trunk allowed vlan 10,20
SW2(config-if)#interface fa0/2
SW2(config-if)#switchport mode trunk
Command rejected: An interface whose trunk encapsulation :
configured to "trunk" mode.
SW2(config-if)#switchport trunk encapsulation dot1q
SW2(config-if)#switchport mode trunk
SW2(config-if)#switchport trunk allowed vlan 10,20
SW2(config-if)#

```

```

SW3(config)#interface fa0/1
SW3(config-if)#switchport mode trunk

SW3(config-if)#
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthet
to down

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthet
to up

SW3(config-if)#switchport trunk allowed vlan 10,20
SW3(config-if)#

```

Task 92

Showing trunk does nothing, and for a reason unknown the show vlan tells me that none of the interfaces I configured are actually in the vlans required

```
SW3#show vlan brief
```

VLAN Name	Status	Ports
1 default	active	Fa0/5, Fa0/6, Fa0/7, Fa0/8 Fa0/9, Fa0/10, Fa0/11, Fa0/12 Fa0/13, Fa0/14, Fa0/15, Fa0/16 Fa0/17, Fa0/18, Fa0/19, Fa0/20 Fa0/21, Fa0/22, Fa0/23, Fa0/24 Gig0/1, Gig0/2
1002 fddi-default	active	
1003 token-ring-default	active	
1004 fddinet-default	active	
1005 trnet-default	active	

```
SW3#show int trunk
```

```
SW3#show interfaces trunk
```

```
SW3#
```

```
SW2>ena
```

```
SW2#show vlan brief
```

VLAN Name	Status	Ports
1 default	active	Fa0/1, Fa0/2, Fa0/3, Fa0/4 Fa0/5, Fa0/6, Fa0/7, Fa0/8 Fa0/9, Fa0/10, Fa0/11, Fa0/12 Fa0/13, Fa0/14, Fa0/15, Fa0/16 Fa0/17, Fa0/18, Fa0/19, Fa0/20 Fa0/21, Fa0/22, Fa0/23, Fa0/24 Gig0/1, Gig0/2
10 ENG	active	
20 SALES	active	
1002 fddi-default	active	
1003 token-ring-default	active	
1004 fddinet-default	active	
1005 trnet-default	active	

```
SW2#show int trunk
```

```
SW2#
```

task 93

```
SW2(config)#int fa0/1
```

```
SW2(config-if)#switchport mode access vlan 10
```

```
% Invalid input detected at '^' marker.
```

```
SW2(config-if)#switchport mode access
```

```
SW2(config-if)#switchport access vlan 10
```

```
SW2(config-if)#exit
```

```
SW2(config)#int fa0/2
```

```
SW2(config-if)#switchport mode access
```

```
SW2(config-if)#switchport access vlan 20
```

```
SW2(config-if)#
```

I really cannot figure out why the interfaces won't show up and it causes the rest of the steps to fail when testing connectivity.