



---

# NAVIGATING THE IOS

---


Packet Tracer week 1




31 JULY 2026  
LERATO MODISE

## Establish Basic Connections, Access the CLI and Explore Help

Connect PC1 to S1 using a console cable



RS 232 connection



Establish a terminal session with S1

```
Boot Sector Filesystem (bs:) installed, fsid: 3
Parameter Block Filesystem (pb:) installed, fsid: 4

Loading "flash:/c2960-lanbase-mz.122-25.FX.bin"...
##### [OK]
Restricted Rights Legend
Use, duplication, or disclosure by the Government is
subject to restrictions as set forth in subparagraph
(c) of the Commercial Computer Software - Restricted
Rights clause at FAR sec. 52.227-19 and subparagraph
(c) (1) (ii) of the Rights in Technical Data and Computer
Software clause at DFARS sec. 252.227-7013.
    cisco Systems, Inc.
    170 West Tasman Drive
    San Jose, California 95134-1706
Cisco IOS Software, C2960 Software (C2960-LANBASEK9-M), Version 15.0(2)SE4, RELEASE
SOFTWARE (fc1)
Technical Support: http://www.cisco.com/techsupport
Copyright (c) 1986-2013 by Cisco Systems, Inc.
Compiled Wed 26-Jun-13 02:49 by mnnguyen
Initializing flashfs...
fsck: Disable shadow buffering due to heap fragmentation.
flashfs[2]: 2 files, 1 directories
flashfs[2]: 0 orphaned files, 0 orphaned directories
flashfs[2]: Total bytes: 32514048
flashfs[2]: Bytes used: 11952128
flashfs[2]: Bytes available: 20561920
flashfs[2]: flashfs fsck took 2 seconds.
flashfs[2]: Initialization complete....done Initializing flashfs.
Checking for Bootloader upgrade..
Boot Loader upgrade not required (Stage 2)
POST: CPU MIC register Tests : Begin
POST: CPU MIC register Tests : End, Status Passed
POST: PortASIC Memory Tests : Begin
POST: PortASIC Memory Tests : End, Status Passed
POST: CPU MIC interface Loopback Tests : Begin
POST: CPU MIC interface Loopback Tests : End, Status Passed
POST: PortASIC RingLoopback Tests : Begin
POST: PortASIC RingLoopback Tests : End, Status Passed
POST: PortASIC CAM Subsystem Tests : Begin
```

Copy  
Paste

Explore the IOS HELP

```
Switch>?
Exec commands:
  connect      Open a terminal connection
  disable      Turn off privileged commands
  disconnect    Disconnect an existing network connection
  enable       Turn on privileged commands
  exit         Exit from the EXEC
  logout       Exit from the EXEC
  ping         Send echo messages
  resume       Resume an active network connection
  show         Show running system information
  ssh         Open a secure shell client connection
  telnet       Open a telnet connection
  terminal     Set terminal line parameters
  traceroute   Trace route to destination
Switch>t?
telnet terminal traceroute
Switch>t te?
% Ambiguous command: "t te"
Switch>te?
telnet terminal
Switch>?
Exec commands:
  connect      Open a terminal connection
  disable      Turn off privileged commands
  disconnect    Disconnect an existing network connection
  enable       Turn on privileged commands
  exit         Exit from the EXEC
  logout       Exit from the EXEC
  ping         Send echo messages
  resume       Resume an active network connection
  show         Show running system information
  ssh         Open a secure shell client connection
  telnet       Open a telnet connection
  terminal     Set terminal line parameters
  traceroute   Trace route to destination
```

## Explore EXEC Modes

```
Switch>en<Tab>
Translating "en<Tab>"...domain server (255.255.255.255)
% Unknown command or computer name, or unable to find computer address

Switch>te<Tab>enable
Translating "te<Tab>enable"...domain server (255.255.255.255)
% Unknown command or computer name, or unable to find computer address

Switch>en
Switch>enable
Switch#?
Exec commands:
clear          Reset functions
clock          Manage the system clock
configure      Enter configuration mode
connect        Open a terminal connection
copy           Copy from one file to another
debug          Debugging functions (see also 'undebug')
delete         Delete a file
dir            List files on a filesystem
disable        Turn off privileged commands
disconnect     Disconnect an existing network connection
enable         Turn on privileged commands
erase          Erase a filesystem
exit           Exit from the EXEC
logout         Exit from the EXEC
more           Display the contents of a file
no             Disable debugging informations
ping           Send echo messages
reload         Halt and perform a cold restart
resume         Resume an active network connection
setup          Run the SETUP command facility
show           Show running system information
ssh            Open a secure shell client connection
telnet         Open a telnet connection
terminal       Set terminal line parameters
```

## SET A CLOCK

```
Switch#show clock
*0:25:51.894 UTC Mon Mar 1 1993
Switch#clock ?
  set  Set the time and date
Switch#clock ?
  set  Set the time and date
Switch#clock 15:00:00 31 Jan 2035
      ^
% Invalid input detected at '^' marker.

Switch#clock?
clock
Switch#clock set ?
  hh:mm:ss  Current Time
Switch#clock set 15:00:00 ?
  <1-31>    Day of the month
  MONTH     Month of the year
Switch#clock set 15:00:00 31 Jan 2035
Switch#show clock
15:0:17.511 UTC Wed Jan 31 2035
```