




```

Router>enable
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#
Router(config)#interface FastEthernet0/0
Router(config-if)#
Router(config-if)#exit
Router(config)#interface FastEthernet0/1
Router(config-if)#ip address 10.10.20.2 255.0.0.0
Router(config-if)#ip address 10.10.20.2 255.255.255.0
Router(config-if)#no shutdown
Router(config-if)#
%LINK-3-UPDOWN: Interface FastEthernet0/1, changed state to down
Router(config-if)#
%LINK-3-CHANGED: Interface FastEthernet0/1, changed state to administratively down
Router(config-if)#exit
Router(config)#interface FastEthernet0/0
Router(config-if)#no shutdown
Router(config-if)#
%LINK-3-CHANGED: Interface FastEthernet0/0, changed state to up
%LINEPROTO-3-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up
Router(config-if)#end
Router#
%SYS-5-CONFIG_I: Configured from console by console
Router>configure terminal
^
% Invalid input detected at '^' marker.
Router>configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#ip domain-lookup
Router(config)#name-server 10.10.10.10
^
% Invalid input detected at '^' marker.
  
```

```
Router#
%SYS-5-CONFIG_I: Configured from console by console

Router#ping 10.10.10.2

Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 10.10.10.2, timeout is 2 seconds:
.....
Success rate is 0 percent (0/5)

Router#ping 10.10.10.2

Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 10.10.10.2, timeout is 2 seconds:
.....
Success rate is 0 percent (0/5)

Router#
Router#
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#interface FastEthernet0/0
Router(config-if)#
Router(config-if)#
Router(config-if)#exit
Router(config)#interface FastEthernet0/0
Router(config-if)#
Router(config-if)#exit
Router(config)#interface FastEthernet0/1
Router(config-if)#
Router(config-if)#exit
Router(config)#interface FastEthernet0/0
Router(config-if)#end
Router#
%SYS-5-CONFIG_I: Configured from console by console

Router#ping 10.10.20.2

Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 10.10.20.2, timeout is 2 seconds:
.!!!!
Success rate is 80 percent (4/5), round-trip min/avg/max = 0/0/0 ms

Router#
```

Router con0 is now available

Press RETURN to get started.

Press RETURN to get started!

```
Router>enable
Router#
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#interface FastEthernet0/0
Router(config-if)#end
Router#
%SYS-5-CONFIG_I: Configured from console by console

Router#clear arp-cache
Router#ping 10.10.10.2

Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 10.10.10.2, timeout is 2 seconds:
!!!!
Success rate is 100 percent (5/5), round-trip min/avg/max = 0/0/2 ms

Router#
```

```
Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 10.10.10.2, timeout is 2 seconds:
!!!!
Success rate is 100 percent (5/5), round-trip min/avg/max = 0/0/2 ms
```

```
Router#show arp


| Protocol | Address    | Age (min) | Hardware Addr  | Type | Interface       |
|----------|------------|-----------|----------------|------|-----------------|
| Internet | 10.10.10.1 | -         | 0003.E473.5C01 | ARPA | FastEthernet0/0 |
| Internet | 10.10.10.2 | 0         | 0090.0CE6.B501 | ARPA | FastEthernet0/0 |


Router#
```

```
Router#show arp


| Protocol | Address    | Age (min) | Hardware Addr  | Type | Interface       |
|----------|------------|-----------|----------------|------|-----------------|
| Internet | 10.10.10.1 | 8         | 0003.E473.5C01 | ARPA | FastEthernet0/0 |
| Internet | 10.10.10.2 | -         | 0090.0CE6.B501 | ARPA | FastEthernet0/0 |
| Internet | 10.10.20.1 | 4         | 0090.2B55.0501 | ARPA | FastEthernet0/1 |
| Internet | 10.10.20.2 | -         | 0090.0CE6.B502 | ARPA | FastEthernet0/1 |


Router#
```

```
Router#show arp
Protocol Address      Age (min) Hardware Addr  Type   Interface
Internet 10.10.20.1          -    0090.2B55.0501  ARPA   FastEthernet0/0
Internet 10.10.20.2           5    0090.0CE6.B502  ARPA   FastEthernet0/0
Router#
```
