


Mpho Edward Makata

Practice 6



28.

```
Router(config)#
Router(config)#hostname R1
R1(config)#
R1(config)#
R1(config)#interface FastEthernet0/0
R1(config-if)#
```

29.

```
Router(config-if)#
Router(config-if)#hostname R2
R2(config)#
R2(config)#
R2(config)#
```

30.

```
R1(config)#
R1(config)#interface FastEthernet0/0
R1(config-if)#
R1(config-if)#ip address 10.10.10.1 255.255.255.0
R1(config-if)#no shutdown
R1(config-if)#
```

31.

```
R2(config)#
R2(config)#interface FastEthernet
% Incomplete command.
R2(config)#interface FastEthernet0/0
R2(config-if)#ip address 10.10.10.2 255.255.255.0
R2(config-if)#no shutdown
R2(config-if)#
```

33.

```
Switch>
Switch>en
Switch#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Switch(config)#
Switch(config)#interface vlan 1
Switch(config-if)#ip address 10.10.10.10 255.255.255.0
Switch(config-if)#no shutdown
```

34.

```
Switch#ping 10.10.10.2

Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 10.10.10.2, timeout is 2 seconds:
.!!!!
Success rate is 80 percent (4/5), round-trip min/avg/max = 0/0/0 ms

Switch#
```

35.

36.

```
R1>show CDP
Global CDP information:
  Sending CDP packets every 60 seconds
  Sending a holdtime value of 180 seconds
  Sending CDPv2 advertisements is enabled
R1>
```

37.

```
R1#show cdp
Global CDP information:
  Sending CDP packets every 60 seconds
  Sending a holdtime value of 180 seconds
  Sending CDPv2 advertisements is enabled
R1#show cdp neighbor
Capability Codes: R - Router, T - Trans Bridge, B - Source Route Bridge
                  S - Switch, H - Host, I - IGMP, r - Repeater, P - Phone
Device ID        Local Intrfce Holdtme  Capability Platform  Port ID
Switch           Fas 0/0      55         S          2960      Fas 0/1
R1#
```

38.

```

R1#show cdp
Global CDP information:
  Sending CDP packets every 60 seconds
  Sending a holdtime value of 180 seconds
  Sending CDPv2 advertisements is enabled
R1#show cdp neighbors
      ^
% Invalid input detected at '^' marker.

R1#show cdp neighbors
Capability Codes: R - Router, T - Trans Bridge, B - Source Route Bridge
                  S - Switch, H - Host, I - IGMP, r - Repeater, P - Phone
Device ID      Local Intrfce  Holdtme    Capability  Platform  Port ID
R1#

```

39.

40.

```

Switch>show ip interface brief

```

Interface	IP-Address	OK?	Method	Status	Protocol
FastEthernet0/1	unassigned	YES	manual	up	up
FastEthernet0/2	unassigned	YES	manual	up	up

41.

```

Switch#
Switch#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
Switch(config)#
Switch(config)#int fa0/2
Switch(config-if)#shutdown

Switch(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/2, changed state to administratively down

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/2, changed state to c

Switch(config-if)#end
Switch#
%SYS-5-CONFIG_I: Configured from console by console

Switch#show ip address brief
      ^
% Invalid input detected at '^' marker.

Switch#show ip interface brief

```

Interface	IP-Address	OK?	Method	Status	Protocol
FastEthernet0/1	unassigned	YES	manual	up	up
FastEthernet0/2	unassigned	YES	manual	administratively down	down
FastEthernet0/3	unassigned	YES	manual	down	down

42.

```

Switch#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Switch(config)#int fa0/2
Switch(config-if)#no shutdown

Switch(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/2, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/2, changed state to up

Switch(config-if)#end
Switch#
%SYS-5-CONFIG_I: Configured from console by console

Switch#
Switch#show ip interface brief

```

Interface	IP-Address	OK?	Method	Status	Protocol
FastEthernet0/1	unassigned	YES	manual	up	up
FastEthernet0/2	unassigned	YES	manual	up	up
FastEthernet0/3	unassigned	YES	manual	down	down

43.

```

Switch(config)#int fa0/2
Switch(config-if)#duplex half
Switch(config-if)#end
Switch#
%SYS-5-CONFIG_I: Configured from console by console

Switch#show interfaces fa0/2
FastEthernet0/2 is up, line protocol is up (connected)
  Hardware is Lance, address is 0001.9700.8702 (bia 0001.9700.8702)
  BW 100000 Kbit, DLY 100 usec,
    reliability 255/255, txload 1/255, rxload 1/255
  Encapsulation ARPA, loopback not set
  Keepalive set (10 sec)
  Half-duplex, 100Mb/s
  input flow-control is off, output flow-control is off
  ARP type: ARPA, ARP Timeout 00:04:00
  Last input 00:00:08, output 00:00:05, output hang never
  Last clearing of "show interface" counters never
  Input queue: 0/75/0/0 (size/max/drops/flushes); Total output drops: 0
  Queueing strategy: fifo
  Output queue :0/40 (size/max)
  5 minute input rate 0 bits/sec, 0 packets/sec
  5 minute output rate 0 bits/sec, 0 packets/sec
    956 packets input, 193351 bytes, 0 no buffer
    Received 956 broadcasts, 0 runts, 0 giants, 0 throttles
    0 input errors, 0 CRC, 0 frame, 0 overrun, 0 ignored, 0 abort
    0 watchdog, 0 multicast, 0 pause input
    0 input packets with dribble condition detected
    2357 packets output, 263570 bytes, 0 underruns
--More--

```

44.

```

Switch#
Switch#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Switch(config)#interface FastEthernet0/1
Switch(config-if)#
Switch(config-if)#exit
Switch(config)#interface FastEthernet0/2
Switch(config-if)#duplex full
Switch(config-if)#end
Switch#
%SYS-5-CONFIG_I: Configured from console by console

Switch#show interfaces fa0/2
FastEthernet0/2 is up, line protocol is up (connected)
  Hardware is Lance, address is 0001.9700.8702 (bia 0001.9700.8702)
  BW 100000 Kbit, DLY 100 usec,
    reliability 255/255, txload 1/255, rxload 1/255
  Encapsulation ARPA, loopback not set
  Keepalive set (10 sec)
  Full-duplex, 100Mb/s
  input flow-control is off, output flow-control is off
  ARP type: ARPA, ARP Timeout 00:04:00
  Last input 00:00:08, output 00:00:05, output hang never
  Last clearing of "show interface" counters never

```

45.

```

Switch(config)#interface FastEthernet0/2
Switch(config-if)#duplex auto
Switch(config-if)#duplex full
Switch(config-if)#speed 100
Switch(config-if)#speed 10
Switch(config-if)#
Switch(config-if)#
Switch(config-if)#end
Switch#
%SYS-5-CONFIG_I: Configured from console by console

Switch#show interfaces fa0/2
FastEthernet0/2 is up, line protocol is up (connected)
  Hardware is Lance, address is 0001.9700.8702 (bia 0001.9700.8702)
  BW 100000 Kbit, DLY 1000 usec,
    reliability 255/255, txload 1/255, rxload 1/255
  Encapsulation ARPA, loopback not set
  Keepalive set (10 sec)
  Full-duplex, 10Mb/s
  input flow-control is off, output flow-control is off

```

46.

```

R2>show ip interface brief

```

Interface	IP-Address	OK?	Method	Status	Protocol
FastEthernet0/0	10.10.10.2	YES	manual	up	up
FastEthernet0/1	unassigned	YES	unset	administratively down	down
Vlan1	unassigned	YES	unset	administratively down	down

```

R2>

```