



Kamohelo Lepita 20251349

NETWORK PRACTICAL WEEK 5



Router0

Physical Config CLI Attributes

IOS Command Line Interface

DRAM configuration is 64 bits wide with parity disabled.
255K bytes of non-volatile configuration memory.
249856K bytes of ATA System CompactFlash 0 (Read/Write)

--- System Configuration Dialog ---

Would you like to enter the initial configuration dialog? [yes/no]: no

Press RETURN to get started!

Router>enable
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname POTCH-R1
POTCH-R1(config)#enable secret Cisco123
POTCH-R1(config)#line console 0
POTCH-R1(config-line)#password Cisco123
POTCH-R1(config-line)#login
POTCH-R1(config-line)#exit
POTCH-R1(config)#banner motd # Unauthorized Access Prohibited
Enter TEXT message. End with the character '#'.

banner motd # Unauthorized Access Prohibited #

POTCH-R1(config)#end
POTCH-R1#
%SYS-5-CONFIG_I: Configured from console by console

Router2

Physical Config CLI Attributes

IOS Command Line Interface

```
--- System Configuration Dialog ---
Would you like to enter the initial configuration dialog? [yes/no]: no

Press RETURN to get started!

Router>enable
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname POTCH-R2
POTCH-R2(config)#enable
% Incomplete command.
POTCH-R2(config)#enable secret Cisco123
POTCH-R2(config)#line console 0
POTCH-R2(config-line)#password Cisco123
POTCH-R2(config-line)#login
POTCH-R2(config-line)#exit
POTCH-R2(config)#banner motd # Unauthorized Access Prohibited #
POTCH-R2(config)#end
POTCH-R2#
%SYS-5-CONFIG_I: Configured from console by console
POTCH-R2#exit
```

Multilayer Switch0

Physical Config CLI Attributes

IOS Command Line Interface

```
--- System Configuration Dialog ---
Would you like to enter the initial configuration dialog? [yes/no]: no

Press RETURN to get started!

Switch>enable
Switch#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Switch(config)#hostname POTCH-SW1
POTCH-SW1(config)#enable secret Cisco123
POTCH-SW1(config)#line console 0
POTCH-SW1(config-line)#password Cisco123
POTCH-SW1(config-line)#login
POTCH-SW1(config-line)#exit
POTCH-SW1(config)#banner motd # Unauthorized Access Prohibited #
POTCH-SW1(config)#end
POTCH-SW1#
%SYS-5-CONFIG_I: Configured from console by console
POTCH-SW1#exit
```