

Option Explicit

Sub DynamicSim()

Dim IPA As Double, WT As Double, DMSO As Double

Dim i As Long

Dim MolRateIPA As Double, MolRateWT As Double, MolRateDMSO As Double

Dim retFlag As Variant

Sheets("Compressor").Select

Dim Temp2 As Double, Temp3 As Double, Vapf2 As Double, Vapf3 As Double, HeatD As Double

Dim HeatInt As Double, Duty1 As Double, Duty2 As Double, DelT As Double, F As Double, T1 As Double, T2 As Double, LMTD As Double

i = 7

Do While i <= 330

IPA = Cells(i, 7).Value

WT = Cells(i, 8).Value

DMSO = Cells(i, 9).Value

Cells(3, 12).Value = IPA

Cells(3, 13).Value = WT

Cells(3, 14).Value = DMSO

retFlag = objCHEMCAD.DynamicRunStep

Temp2 = Cells(3, 16).Value

Vapf2 = Cells(3, 17).Value

Temp3 = Cells(3, 18).Value

Vapf3 = Cells(3, 19).Value

HeatD = Cells(3, 20).Value

HeatInt = Cells(3, 21).Value

Duty1 = Cells(3, 22).Value

Duty2 = Cells(3, 23).Value

DelT = Cells(3, 24).Value

LMTD = Cells(3, 25).Value

T1 = Cells(3, 26).Value

T2 = Cells(3, 27).Value

F = Cells(3, 28).Value

Cells(i, 12).Value = Temp2

Cells(i, 13).Value = Vapf2

Cells(i, 14).Value = Temp3

```
Cells(i, 15).Value = Vapf3  
Cells(i, 16).Value = HeatD  
Cells(i, 17).Value = HeatInt  
Cells(i, 18).Value = Duty1  
Cells(i, 19).Value = Duty2  
Cells(i, 20).Value = DelT  
Cells(i, 21).Value = LMTD  
Cells(i, 22).Value = T1  
Cells(i, 23).Value = T2  
Cells(i, 24).Value = F
```

```
i = i + 1
```

Loop

Call RestoreToInitialState

End Sub