



CAPRIOLE PRECAST ENGINE · V1.1

# Cloud Sign-In User Manual

How to Connect to Cloud Patches  
from the Precast Production Engine



**Audience:** All Engine Users

**Server:** [cloud.capriolegroup.org](https://cloud.capriolegroup.org)

**Issued:** May 2026



**Your App Password is personal.  
Never share it with anyone outside your team.**

# 1. Why Sign In to the Cloud?

The Precast Engine stores every project as a **patch file** on Capriole's private ownCloud server ( [cloud.capriolegroup.org](https://cloud.capriolegroup.org) ). Signing in lets you:

| Feature              | Without Sign-In  | After Sign-In                         |
|----------------------|------------------|---------------------------------------|
| View running patches | ✗ Not visible    | ✓ All patches load on home screen     |
| Open a project       | Local files only | ✓ One-click open from cloud card      |
| Save progress        | Local file only  | ✓ Auto-saved to cloud for team access |
| Team collaboration   | ✗ Not possible   | ✓ Everyone sees the same live data    |

**i** The engine uses **ownCloud App Passwords** — not your regular ownCloud login password. An App Password is a special one-time credential you generate yourself inside ownCloud. This keeps your main account secure.

## 1.1 What You Will Need

- Access to **cloud.capriolegroup.org** (ask your IT admin if you don't have an account)
- Your ownCloud **username**
- An **App Password** generated from ownCloud Settings (see Section 2)
- Internet connection

## 1.2 Supported Platforms

The Precast Engine runs in any modern web browser. Recommended browsers:

✓ **Google Chrome**

✓ **Microsoft Edge**

⚠ **Firefox (may block popups)**

## 2. Create an App Password in ownCloud

You must do this **once** before you can sign in to the engine. Your App Password is a 19-character code in the format `xxxx-xxxx-xxxx-xxxx`.

- 1 Open your web browser and go to:  
`cloud.capriolegroup.org`  
Log in with your normal ownCloud **username and password**.
- 2 Click your **profile picture or initials** in the **top-right corner** of the screen.
- 3 From the dropdown menu, click **Settings**.
- 4 In the left sidebar, click **Security**.
- 5 Scroll down to the **"App passwords / tokens"** section.
- 6 In the *App name* field, type: `Precast Factory`  
Then click **Create new app password**.
- 7 ownCloud will display a password in the format `xxxx-xxxx-xxxx-xxxx`.  
**Copy it immediately** — it will only be shown once.

**ownCloud** · cloud.capriolegroup.org

Personal

**Security**

Sharing

Notifications

### App passwords / tokens

Create app passwords for your apps, scripts, or external services. These passwords allow access to your ownCloud account without using your main password.

Precast Factory

Create new app password

**App password created!**

Username: **your.name**

Password: **aBcD-1234-EfGh-5678**

**Copy this password now — it will not be shown again!**



**Copy the App Password before closing the dialog.** ownCloud will never show it again. If you lose it, you must delete it and create a new one.




Save your App Password in a secure place such as your phone's notes or a password manager. You will only need to enter it once per device in the Precast Engine.

### 3. Sign In to the Precast Engine

Once you have your ownCloud username and App Password, follow these steps to connect:

- 1 Open the Precast Engine in your browser and wait for the home screen to load.  
You will see the message: "Not signed in —  Sign In to connect to your cloud running patches"
- 2 Click any of the following buttons — they all open the same sign-in dialog:
  - 3  **Sign In to Cloud** — large button in the top-right of the home screen
  - 4  **Sign In** — small button in the Running Patches section header
  - 5  **Sign In** underlined link in the status text



- 3 The **Sign In dialog** will appear. Enter your details:

 **Sign in to Cloud** 

Capriole ownCloud · cloud.capriolegroup.org

USERNAME

firstname.lastname

APP PASSWORD

.....

ownCloud → Settings → Security → App passwords → create "Precast Factory"

Connect →

 Test Connection

| Field               | What to Enter                                                                                           |
|---------------------|---------------------------------------------------------------------------------------------------------|
| <b>Username</b>     | Your ownCloud username<br>e.g. <code>john.doe</code>                                                    |
| <b>App Password</b> | The 19-character code you generated in ownCloud (Section 2)<br>format: <code>xxxx-xxxx-xxxx-xxxx</code> |


 Click  **Test Connection** first to verify your credentials before clicking Connect.

- 4 Click **Connect** →. The dialog will close and the home screen will refresh.
- 5 The Running Patches section will show  **Connected** in green and display all your project cards.



## 4. After Sign-In — Reading the Home Screen

Once connected, the home screen displays all your running patches as cards. Each card shows key project metrics loaded from the cloud.



| Card Element   | Description                                                         |
|----------------|---------------------------------------------------------------------|
| Project name   | Click anywhere on the card to open the project instantly            |
| Progress bar   | % of panels marked as Cast — updates each time you open the project |
| Metrics strip  | Buildings · Types · Working Days · Concrete m <sup>3</sup>          |
| Edit button    | Add Project No., Building Ref, and Floor details to the card        |
| Cards /  Table | Toggle between card grid and compact table list of all patches      |
| Refresh        | Reload the patch list from the cloud (clears any cached data)       |

Your credentials are saved securely in the browser. You will **not need to sign in again** on the same device unless you clear browser data or use a different browser.

## 5. Troubleshooting

### 5.1 Common Error Messages

| Error Message                                        | Cause                                                    | Fix                                                                                                                                                 |
|------------------------------------------------------|----------------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>✗ Auth failed — check username / app password</b> | Wrong username or App Password entered                   | Re-open Sign In dialog and re-enter both fields. Make sure to use your <b>App Password</b> , not your main ownCloud password                        |
| <b>Failed to load — HTTP 404</b>                     | Project folder not found on server                       | Contact your administrator — the cloud folder may have been moved or renamed                                                                        |
| <b>⚠ Offline — showing cached patches</b>            | No internet connection or server temporarily unavailable | Check your network connection and click  <b>Refresh</b> to retry |
| <b>✗ Network error / Failed to fetch</b>             | Browser blocked the request (CORS or firewall)           | Use Google Chrome or Microsoft Edge. Contact IT if the issue persists                                                                               |

### 5.2 App Password Expired or Lost

- 1 Go to [cloud.capriolegroup.org](https://cloud.capriolegroup.org) and sign in with your main password.
- 2 Navigate to **Settings** → **Security** → **App passwords / tokens**.
- 3 Find the *Precast Factory* entry and click the  **Delete** (bin) icon next to it.
- 4 Create a new App Password following the steps in Section 2.
- 5 Return to the Precast Engine, click  **Sign In**, and enter your username and the new App Password.

### 5.3 Re-authenticate (Quick Fix)

If you see a red error on the home screen with a **Re-authenticate** link, click it directly — it opens the Sign In dialog immediately without navigating away.

 If you switch computers or use a private/incognito browser window, you will need to sign in again. Your credentials are stored per browser, not per user account.

### 5.4 Quick Reference — Sign-In Steps

#### One-time setup (do once per device)

1. Log in to [cloud.capriolegroup.org](https://cloud.capriolegroup.org)
2. Go to **Settings** → **Security** → **App passwords**
3. Create password named [Precast Factory](#) → copy the code

#### Every time you open the engine

1. Click  **Sign In to Cloud** on the home screen
2. Enter your ownCloud **username**

3. Paste your **App Password** ( xxxx-xxxx-xxxx-xxxx )
4. Click **Connect** →
5. Your patches appear — click any card to open a project