MATLAB® Production Server™

Licensing on the Cloud

R2018a

How to Contact MathWorks

Latest news: www.mathworks.com

Sales and services: www.mathworks.com/sales_and_services

User community: www.mathworks.com/matlabcentral

Technical support: www.mathworks.com/support/contact_us

Phone: 508-647-7000

The MathWorks, Inc.
1 Apple Hill Drive
Natick, MA 01760-2098

Licensing MPS on the Cloud

© COPYRIGHT 2018 by The MathWorks, Inc.

Revision History

Month Year   New for Version XXX (Applies to Release Name)
Month Year   Revised for Version XXX (Applies to Release Name)

Licensing for MATLAB® Production Server™ on the Cloud

To set up your license for MATLAB® Production Server™ on the cloud:

- You must have a MathWorks® Account.
- The MATLAB® license you are using must be current on Software Maintenance Service. Learn more.
- You (or end user) must be running MATLAB R2018a.

Note: If you do not have a MATLAB Production Server license, you can request a trial.

End Users

This workflow is for admins only. Contact your admin for instructions on connecting to MATLAB® Production Server™ on the cloud.

Admins

Verify Eligibility

Log in to your MathWorks Account to verify whether your MATLAB Production Server™ license is eligible for R2018a.
Keep the MathWorks Account web page open. You need it to complete activation.

Setup MATLAB Production Server in the Cloud

For more information, see https://insidelabs-git.mathworks.com/cloud/azure/ref/mps.

Activate License

> **Note:** If you previously activated a MATLAB Production Server license, stop the license manager software on your license server. You can stop the license manager using LMTOOLS (Windows®) or lmdown (Linux®/macOS). After stopping the license manager, remove the license file.

1. Log in to the MATLAB Production Server Cloud Console using the username and password you created while setting up your cluster.
2. In the cloud console, go to **Administration** > **Manage License**. Copy the license server MAC address that is displayed.
3. Log in to your MathWorks Account.
4. In the **My Software** section, select the MATLAB Production Server license.
5. In the **Install and Activate** tab, deactivate any existing license, and select the following options:
   Release: R2017b or R0218a
   Operating System: Windows
   Host ID: Paste the license server MAC address that you copied from the cloud console.
   Activation Label: Provide an easily identifiable name.
   Click **Continue**.
6. When asked if the software is installed, select **Yes**. Click **Continue**.
7. Click **Download License File** to download the license file to your computer. Click **Done**.
   Upload the license file to the cloud console.