
HOW TO FIND YOUR LOCAL IP ADDRESS?


Terminal command

• Windows: > ipconfig

• Linux: \$ ip a

Local IP address format is 192.168.XXX.XXX





```
File Edit View Search Terminal Help


(base) [hyacinthe@hyacinthe-Lenovo-Y0GA-C930-13IKB ~]$ ip a

1: lo: <LOOPBACK,UP,LOWER UP> mtu 65536 qdisc noqueue state UNKNOWN group default qlen 1000
link/loopback 00:00:00:00:00 brd 00:00:00:00:00
inet 127.0.0.1/8 scope host lo
valid lft forever preferred lft forever
inet6::1/128 scope host
valid_lft forever preferred!Pft forever

2: wlp10750: <BROADCAST,MULTICAST,UP,LOWER UP> mtu 1500 qdisc noqueue state UP group default qlen 1000
link/ether 18:1d:ea:9e:9b:16 brd ff:ff:ff:ff:ff
inet 192.168.108.164/24 brd 192.168.108.255 scope global dynamic noprefixroute wlp10750
valid lft 561sec preferred lft 561sec
inet6 fe80::fe03:7326:48b1:1a22/64 scope link noprefixroute
valid lft forever preferred_lft forever

(base) [hyacinthe@hyacinthe-Lenovo-Y0GA-C930-131KB ~]$ [
```

HOW TO START PHP BUILT-IN WEB SERVER?



- 1. Go to the directory of the activity (use the command > cd ("change directory"))
- 2. Use terminal command > php -S <ip>:<port> (Capital 'S'!) <ip> = Your IP address <port> = use any number between 1024 and 9999, for example 8080

```
C:\WINDOWS\system32\cmd.exe-php -S 192.168.108.17:8080 — X

Microsoft Windows [Version 10.0.19042.1466]
(c) Microsoft Corporation. All rights reserved.

C:\Users\Hyacinthe>php -S 192.168.108.17:8080
[Fri Feb 11 09:55:14 2022] PHP 8.1.1 Development Server (http://192.168.108.17:8080) started
```

LOCALHOST

The same computer can be at the same time server and client!

As a server, how can you access the site you are hosting?

3 solutions:

- 1. http://<local_network_ip>:<port>
 - \rightarrow Like the other clients!
- 2. http://127.0.0.1:<port>
 - → 127.0.0.1 is special IP address redirecting to your own computer
- 3. http://localhost:<port>
 - \rightarrow localhost resolves to 127.0.0.1

For web development: No need 2 computers, and no need to know your IP

APACHE

PHP built-in server is fine for development only

Start Apache then visit http://localhost (on default port 80!)



You can change the content of the folder xampp/htdocs to change the default content to your website!

