

```
Select Command Prompt
   Autoconfiguration Enabled . . . . : Yes

Wireless LAN adapter Wi-Fi 2:

   Connection-specific DNS Suffix  . :
   Description . . . . . . . . . . . : Intel(R) Dual Band Wireless-AC 8265 #2
   Physical Address. . . . . . . . . : 0C-54-15-B9-82-23
   DHCP Enabled. . . . . . . . . . . : Yes
   Autoconfiguration Enabled . . . . : Yes
   Link-local IPv6 Address . . . . . : fe80::60c5:b7d3:b3d8:9925%3(Preferred)
   IPv4 Address. . . . . . . . . . . : 192.168.0.131(Preferred)
   Subnet Mask . . . . . . . . . . . : 255.255.255.0
   Lease Obtained. . . . . . . . . . : Thursday, 16 April 2026 12:41:45 AM
   Lease Expires . . . . . . . . . . : Sunday, 19 April 2026 2:58:29 PM
   Default Gateway . . . . . . . . . : 192.168.0.1
   DHCP Server . . . . . . . . . . . : 192.168.0.1
   DHCPv6 IAID . . . . . . . . . . . : 51139605
   DHCPv6 Client DUID. . . . . . . . : 00-01-00-01-25-82-B1-14-54-EE-75-FA-31-66
   DNS Servers . . . . . . . . . . . : 192.168.0.1
   NetBIOS over Tcpip. . . . . . . . : Enabled

Ethernet adapter Bluetooth Network Connection:

   Media State . . . . . . . . . . . : Media disconnected
   Connection-specific DNS Suffix  . :
   Description . . . . . . . . . . . : Bluetooth Device (Personal Area Network)
   Physical Address. . . . . . . . . : 0C-54-15-B9-82-27
   DHCP Enabled. . . . . . . . . . . : Yes
   Autoconfiguration Enabled . . . . : Yes
```

As we can see in the screenshot of my Command line “ifconfig” prompt.

1. The IP Address of my device is 192.168.0.131.
   This is a typical home network IP address
2. The subnet mask of my device is 255.255.255.0
   This tells us that this network has 24 network bits and the rest of the bits in the 32 bit address are host bits
3. The Default Gateway which is the routers IP Address and how we appear to server outside our home network is : 192.168.0.1
4. We have 256 Addresses in our subnet but since one is taken but the host and the other by the router we have 254 usable hosts in the subnet