

Lab-6: Calling ARM assembly subroutine from C/C++ program and ARM processor performance analysis

Name: _____

Date: _____

Learning Objectives:

- Create a program in C/C++ and assembly that calls an assembly subroutine from a C/C++ program.
- Analyze the performance of the ARM processor based on experimental results.

Introduction

This laboratory exercise introduces you to the coding framework used to integrate assembly subroutines into C/C++ programs.

Why Integrate Assembly Subroutines into C/C++ Programs?

Reasons for integrating assembly subroutines into C/C++ programs include:

- 1) Optimization of a performance critical function.
 - Manually programming in assembly may result in improved performance compared to compiler-generated code.
- 2) Availability of processor-specific instructions that a compiler may not utilize.
- 3) Direct access to hardware.

Calling Assembly Subroutines from a C/C++ Program

To call an assembly subroutine stored in a different source file from a C/C++ program the following requirements must be satisfied:

- 1) Assembly code must use the “EXPORT” or “GLOBAL” directive to make the assembly subroutine accessible by the C/C++ program.
- 2) C/C++ program must declare the assembly subroutine as a function using the “extern” keyword.

Also, the input arguments and return value of the C/C++ function corresponding to the assembly subroutine map to specific register locations according to the ARM embedded application binary interface (EABI). As shown in Fig. 1, the first four, 32-bit input arguments map to registers R0 – R3, respectively, and a 32-bit return value maps to R0.




Figure 1 – Register to Argument and Register to Return Value Mappings for ARM EABI

Prelab

For your prelab activity, you will create a project that consists of 2 files: main.cpp and add_asm.s. The code in main.cpp will add two integers together and print the sum to the terminal screen. The two integers are added by calling an assembly subroutine written in add_asm.s. The code for each file is listed below

main.cpp

```
#include "mbed.h"

extern "C" int add_asm(int a, int b);

int main() {
    while (true) {
        printf("add_asm computes %d + %d = %d\n", 2, 3, add_asm(2,3));
        wait(0.5);
    }
}
```


add_asm.s

```
AREA  | .text|, CODE, READONLY


add_asm    PROC
EXPORT add_asm
ADD    R0, R1
BX    LR
ENDP
ALIGN
END
```

You will use Arm Keil Studio to create this project. To do this successfully, follow the instructions below.


1. Create a new Mbed project in Arm Keil Studio called Lab_6_Prelab by doing the following:
 - i. Select **File > New > Mbed Project option** in the upper left corner of the IDE.




- ii. In the **New Project** dialog box, under **Example project**, select **Mbed 2 → mbed2-example-blinky**.



- iii. Enter **Lab_6_Prelab** under Project Name and click Add Project.




- iv. This will create a new project folder in your Project Workspace tree with the name **Lab_6_Prelab**. Select the **main.cpp** file.




- v. Copy and paste the code given for **main.cpp** into this file and save it.

- vi. Right-click the **Lab_6_Prelab** Folder and select **New File**.



- vii. Under the New File dialog box, enter **add_asm.s** and click **OK**.



- viii. **Copy and paste the code given for add_asm.s into this file and save it.**
- ix. Your program is now ready to compile, build and run. Click button to run (build and download) the project. Sometimes this fails, if this is the case click button to build the project, then manually download the project.
- x. **Open your terminal program** (Putty or CoolTerm). Verify that the terminal displays the following every 0.5 s.:

```
add_asm computes 2 + 3 = 5
```

- xi. **Take a screenshot of terminal output.**

Laboratory Procedure:

For the lab, you will use the C++ program and assembly subroutine structure introduced in the prelab to create a program that allows you to control on/off time of your board's blinking led. Your project will consist of 2 files: main.cpp and delay_asm.s, which are given below.

The code in main.cpp creates a DigitalOut object `myled` that you map to LED1 of your microcontroller. You invert the state of `myled` within the `while(true)` loop to turn your led on and off repetitively. The call to assembly subroutine `delay_asm()` creates a delay before the next iteration of the `while(true)` loop, which means that `delay_asm()` controls the on/off time of LED1. The Timer object `t` is used to measure the on/off time in software and enables you to print the on/off time to the terminal screen.

main.cpp

```
#include "mbed.h"

DigitalOut myled(LED1);
Timer t;

extern "C" void delay_asm(void);

int main() {
    int begin, end;

    while(true) {
        t.start();           // start timer
        begin = t.read_ms();

        myled = !myled;      // invert LED state
        delay_asm();         // sets led on/off time

        end = t.read_ms();
        t.stop();            // stop timer
        printf("LED on/off time = %d ms \n", end - begin);
    }
}
```

The code in delay_asm.s uses register R0 to control the delay time. It does this by loading an initial value into R0, then repetitively decrements the value stored in R0 by 1 until R0 == 0. When R0 == 0, execution switches back to main.cpp. This means that the execution time of delay_asm() is determined by the initial value of R0.

delay_asm.s

```
        AREA    | .text |, CODE, READONLY

delay_asm PROC
EXPORT delay_asm
LDR R0, =0x00800000      ;set initial value of R0
MOV R1, #1
LOOP    SUBS R0, R1
BNE LOOP
BX LR
ENDP
ALIGN
END
```

1. Using the procedure described in the Prelab, **create a program called Lab_6_delay_asm in the Arm Keil Studio IDE**. Lab_6_delay_asm will have 3 components.
 - a. main.cpp (code given above)
 - b. delay_asm.s (code given above)
 - c. Mbed 2 library
2. **Build/Run the program.**

3. **Record the on/off time** of your LED using your terminal application.

LED on/off Time:

4. The initial value of R0 determines the on/off time of the LED. **Convert the initial value of R0 into decimal and compute the ratio** of R0 value to LED on/off time.

Ratio of R0 value to LED on/off Time:

5. Modify the initial value of R0 and observe the change in on/off time of the LED.
6. Use the ratio from 4 to determine the initial value of R0 in hexadecimal that will give an LED on/off time of 1 ms.

R0 Setting for 1 ms on/off Time:

Discussion Questions

1. Refer to Table 3.1. Cortex-M4 Instruction Set Summary at the url below, and describe in your own words the operations accomplished by the MOV and SUBS instructions in the delay_asm.s file.
<https://developer.arm.com/documentation/ddi0439/b/Programmers-Model/Instruction-set-summary/Cortex-M4-instructions?lang=en>
2. The largest value that can be stored in R0 is 0xFFFFFFFF. What is the longest on/off time (in seconds) you can achieve using `delay_asm()`?
3. An inspection of Table 3.1 will show that each instruction takes a specific number of clock cycles to execute. Use the clock cycle information from Table 3.1 to determine the number of clock cycles it takes to execute all the instructions in `delay_asm()`. Note the following:
 - a. The executable instructions run from line 5 to 9.
 - b. Instructions on lines 7 and 8 repeat multiple times until `R0 == 0`.
 - c. Assume that $P = 1$ for computing the number of cycles corresponding to the BNE instruction.
4. Using the result from 3 and your on/off time measurement, estimate the clock rate of your processor in Hz (clock cycles per second).

Report Requirements

Prelab

Screenshot of terminal output (30 points)

Lab Results

- Video of blinking LED (10 points)
Please post the video link only when you submit under the D2L Assignments folder.
- LED on/off time (10 points)
- Ratio of R0 value to LED on/off Time (10 points)
- R0 Setting for 1 ms on/off Time. (10 points)

Answers to Discussion Questions

1. 10 points
2. 10 points
3. 5 points
4. 5 points

No formal lab report is needed for this lab.