Adobe CQ5 Brightcove Connector

Contents


Installation	. 2
API Token Configuration	. 2
Configuration of default Video Player Component	
Configuration of default Playlist Component	
Using Video and Playlist Components	

Installation

- 1. Download repository from github
- 2. Build it using mvn clean install command
- 3. Upload zip into CQ instance

API Token Configuration


- Get your API Tokens from Brightcove Video Cloud: https://videocloud.brightcove.com/admin/api
- 2. Modify the ReadToken value in Adobe CQ Web Console Configuration -> Brightcove Service to match your API Token



Configuration of default Video Player Component

Here you will configure the default values for the playerID and playerKey properties of the basic Brightcove Video component

- 1. Navigate to https://videocloud.brightcove.com/publishing
- 2. Select player which does not support playlist
- 3. Click Get Code on the bottom, and select JavaScript



4. In the given snippet please find:

<param name="playerID" value="2256181772001" />

<param name="playerKey" value="AQ~~,AAACDQK-</pre>

Vzk~,HdO098T0k7UdvBy4XuRJGfjNVK-fVFVx"/>Configuration of default

- 5. Copy **playerID** value and paste it into **Default Video Player ID** field in Brightcove Service Configuration
- 6. Copy **playerKey** value and paste it into **Default Video Player Key** field in Brightcove Service Configuration

Configuration of default Playlist Component

Here we will setup the playerId and playerKey properties for the BrightcovePlaylist component.

The configuration of the Brightcove Playlist component is nearly identical to set up for the Video Player component, except the user must select a videoPlayer that is compatible for playlists. S

So once again:

- 1. 1. Navigate to https://videocloud.brightcove.com/publishing
- 2. Select player which supports playlist
- 3. Click Get Code on the bottom, and select JavaScript

4. In the Given snippet please find

<param name="playerID" value="3570927420001" />

<param name="playerKey" value="AQ~~,AAACDQK-Vzk~,HdO098T0k7XEYQYVIWHGmliWaJq9aG_q"
/>

- 5. Copy **playerID** value and paste it into **Default Playlist Player ID** field in Brightcove Service Configuration
- 6. Copy **playerKey** value and paste it into **Default Playlist Player Key** field in Brightcove Service Configuration

In case of any problem, please see screen shot in **Configuration of default Video Player Component** section.

Using Video and Playlist Components

1. By default Brightcove components are available in General section in side-kick



- 2. Configuration contains two tabs:
 - a. General in this tab you can specify size of video player, component alignment and you can select Birhgtcove Video (or playlist for Brightcove Playlist Component) from the dropdown
 - b. Account Settings in this tab you can specify other than default Video Player (or Playlist Player for Brightcove Playlist Component) by providing its ID and Key. Default value is taken from **Brightcove Service Configuration**

