

Cultivo Carnivores

Seed starter pack - Sowing Instructions

- Open the plastic container. Remove the polystyrene cup and punch a few drainage holes into the bottom
- Empty the growing media contents into a microwave safe container. Add water and leave overnight to moisten the growing substrate thoroughly - distilled or reverse osmosis water preferred - 500ml should be sufficient. Media can also be pre-moistened to speed up the process
- Place the container into the microwave at full power for a 1-2 minutes to kill any spores in the media
- Let the media cool down completely and empty the contents into the plastic plant pot, insert the plant pot into the polystyrene cup (the polystyrene will help control temperature changes and eliminate the risk of overheating fragile seedling roots)
- Open the seed packet carefully - some seeds are tiny!
- Level the growing media and spread the seeds on the surface without burying them - they need light to germinate
- Use a spray bottle - distilled or reverse osmosis water preferred - and mist the surface to ensure the seeds make proper contact with the moist media
- Place the polystyrene container into the plastic cup. Add enough water to the plastic container so the polystyrene cup is partially submerged in the water - let the water level fluctuate, change water weekly or more frequently if discolouration occurs. Use a fine water mist on the soil surface and cap every 3-4 days if necessary - make sure the media does not dry out, but also not soggy - you don't want floating seeds
- Open the ventilation hole on the cap completely, mist the cap and secure it onto the plastic container to maintain a humid growth environment
- Place the growing chamber in a warm place with **STRONG**, indirect light. A couple hours of early morning sun will suffice but take caution as direct sun will cause heat to build up under the cap and can cook the seeds
- If grown indoors / sunny windowsill, consider using a desk lamp (A daylight CFL bulb works great) to supplement light - a light cycle of 12-14 hours is recommended
- Most seeds sprout in temperatures of 20-30 degrees Celcius, a day-night temperature difference of 10 degrees may also prove useful. A heating pad can be used to keep seeds warm
- Remember to label your seeds and record the sowing date
- Most seeds take 4-10 weeks to germinate - some sooner, some much later. The main germination factors are warmth, humidity and **VERY** bright light
- **BE PATIENT** - observe for growth through the clear cap. Try not to disturb the seedlings. If you notice algae developing on the surface - improve airflow
- Once your seeds have sprouted introduce the seedlings to the outside world by removing the cap for increased periods every day - removing it completely over a period of a week
- Once acclimatised you can remove the plastic plant pot from the container without the need to repot, and your new carnivores can continue growing in a more permanent location

Happy Growing!!