

# Namespace RonCS

## Classes

### [Ron](#)

Ron Serialization/Deserialization API.

### [RonExcludeAttribute](#)

Field should not be serialized in a ron document.

### [RonFromAttribute](#)

Marks a method as a candidate for RonFrom conversion when Serializing or Deserializing.

### [RonIncludeAttribute](#)

Element should always be serialized, regardless of visibility.

### [RonIntoAttribute](#)

Indicates that method can be used for ron auto conversion.

### [RonListAttribute](#)

Marks a class or field as a list.

### [RonMapAttribute](#)

Marks a class or field as a ron map.

### [RonPrintOptions](#)

Ron print options.

### [RonProxyAttribute](#)

Indicates that a class should be converted to or from the proxy type for serialization.

### [RonTupleAttribute](#)

Marks a method that should be used to serialize the element as a ron tuple.

### [SerializationContext](#)

Context for serializing ron elements. Custom overrides for Ron are stored in the local or global serialization context.

### [TypeConversionExtensions](#)

Extension methods for converting ron objects.

## Interfaces

### [TypeSerializerConverter](#)

Base interface for serialization converters. Serialization converters convert C# objects into Ron AST nodes.

## Enums

### [RonPrintMode](#)

The print mode to use for Ron printing.

# Class Ron

Namespace: [RonCS](#)

Assembly: RonCS.dll

Ron Serialization/Deserialization API.

```
public static class Ron
```

## Inheritance

[object](#)  ← Ron

## Inherited Members

[object.Equals\(object\)](#) , [object.Equals\(object, object\)](#) , [object.GetHashCode\(\)](#) ,  
[object.GetType\(\)](#) , [object.MemberwiseClone\(\)](#) , [object.ReferenceEquals\(object, object\)](#) ,  
[object.ToString\(\)](#) 

## Methods

### Deserialize(string, Type?)

Deserialize the input, or throw an exception if failed.

```
public static object? Deserialize(string source, Type? hint)
```

## Parameters

source [string](#) 

hint [Type](#) 

## Returns

[object](#) 

### Parse(string)

Parse the source and return the resulting ron document. Throw an exception if not successful.

```
public static RonDocument Parse(string source)
```

## Parameters

source [string](#)

## Returns

[RonDocument](#)

## RegisterDictionaryType(Type)

Register a type to serialize as a dictionary.

```
public static void RegisterDictionaryType(Type type)
```

## Parameters

type [Type](#)

## RegisterListType(Type)

Register a type to serialize as a list.

```
public static void RegisterListType(Type type)
```

## Parameters

type [Type](#)

## RegisterProxyType(Type, Type)

Register a proxy type for another type.

```
public static void RegisterProxyType(Type sourceType, Type proxyType)
```

## Parameters

sourceType [Type](#)

proxyType [Type](#)

## RegisterTupleConverter<T>(Func<T, object[]>)

Register custom tuple converter for type.

```
public static void RegisterTupleConverter<T>(Func<T, object[]> converter)
```

## Parameters

converter [Func](#)<T, [object](#)[]>

## Type Parameters

T

## RegisterType(params Type[])

Register a type that ron knows how to deserialize. When Ron cannot infer a type from context it will check the type cache for a registered type.

```
public static void RegisterType(params Type[] types)
```

## Parameters

types [Type](#)[]

## RegisterTypeConverter(Type, TypeSerializerConverter)

Register a serialization converter for a known type.

```
public static void RegisterTypeConverter(Type type, TypeSerializerConverter converter)
```

## Parameters

type [Type](#)

converter [TypeSerializerConverter](#)

## ResetGlobalContext()

Clear all settings in the global context.

```
public static void ResetGlobalContext()
```

## Serialize(object, RonPrintOptions)

Convert an object to a ron string.

```
public static string Serialize(object source, RonPrintOptions options = null)
```

## Parameters

source [object](#)

options [RonPrintOptions](#)

## Returns

[string](#)

## TryDeserialize(string, Type?, out object?)

Try to deserialize the result

```
public static bool TryDeserialize(string source, Type? typeHint, out object? output)
```

## Parameters

source [string](#)

typeHint [Type](#)

output [object](#)

## Returns

[bool](#)

## TryDeserialize(string, Type?, out object?, out Exception)

Try to deserialize the input, returning an object if successful, or an exception if failed.

```
public static bool TryDeserialize(string source, Type? typeHint, out object? output,
out Exception exception)
```

## Parameters

source [string](#)

typeHint [Type](#)

output [object](#)

exception [Exception](#)

## Returns

[bool](#)

## TryParse(string, out RonDocument)

Try to parse the source, returning the document if successful.

```
public static bool TryParse(string source, out RonDocument document)
```

## Parameters

source [string](#)

document [RonDocument](#)

## Returns

[bool](#)

## TryParse(string, out RonDocument, out Exception)

Try to parse the source, returning the document if successful, or the exception if not successful.

```
public static bool TryParse(string source, out RonDocument document, out  
Exception exception)
```

## Parameters

source [string](#)

The source document to parse.

document [RonDocument](#)

The document if successful.

exception [Exception](#)

The exception thrown if not successful.

## Returns

[bool](#)

## TryTokenize(string, out TokenList<RonTokenKind>, out Exception)

Try to tokenize the input. If successful returns the result. Otherwise returns the exception.

```
public static bool TryTokenize(string source, out TokenList<RonTokenKind> result,  
out Exception exception)
```

## Parameters

source [string](#)

result TokenList<[RonTokenKind](#)>

exception [Exception](#)

## Returns

[bool](#)

# Class RonExcludeAttribute

Namespace: [RonCS](#)

Assembly: RonCS.dll

Field should not be serialized in a ron document.

```
[AttributeUsage(AttributeTargets.Property|AttributeTargets.Field)]  
public class RonExcludeAttribute : Attribute
```

## Inheritance

[object](#)  ← [Attribute](#)  ← RonExcludeAttribute

## Inherited Members

[Attribute.Equals\(object\)](#)  , [Attribute.GetCustomAttribute\(Assembly, Type\)](#)  ,  
[Attribute.GetCustomAttribute\(Assembly, Type, bool\)](#)  ,  
[Attribute.GetCustomAttribute\(MemberInfo, Type\)](#)  ,  
[Attribute.GetCustomAttribute\(MemberInfo, Type, bool\)](#)  ,  
[Attribute.GetCustomAttribute\(Module, Type\)](#)  ,  
[Attribute.GetCustomAttribute\(Module, Type, bool\)](#)  ,  
[Attribute.GetCustomAttribute\(ParameterInfo, Type\)](#)  ,  
[Attribute.GetCustomAttribute\(ParameterInfo, Type, bool\)](#)  ,  
[Attribute.GetCustomAttributes\(Assembly\)](#)  , [Attribute.GetCustomAttributes\(Assembly, bool\)](#)  ,  
[Attribute.GetCustomAttributes\(Assembly, Type\)](#)  ,  
[Attribute.GetCustomAttributes\(Assembly, Type, bool\)](#)  ,  
[Attribute.GetCustomAttributes\(MemberInfo\)](#)  ,  
[Attribute.GetCustomAttributes\(MemberInfo, bool\)](#)  ,  
[Attribute.GetCustomAttributes\(MemberInfo, Type\)](#)  ,  
[Attribute.GetCustomAttributes\(MemberInfo, Type, bool\)](#)  ,  
[Attribute.GetCustomAttributes\(Module\)](#)  , [Attribute.GetCustomAttributes\(Module, bool\)](#)  ,  
[Attribute.GetCustomAttributes\(Module, Type\)](#)  ,  
[Attribute.GetCustomAttributes\(Module, Type, bool\)](#)  ,  
[Attribute.GetCustomAttributes\(ParameterInfo\)](#)  ,  
[Attribute.GetCustomAttributes\(ParameterInfo, bool\)](#)  ,  
[Attribute.GetCustomAttributes\(ParameterInfo, Type\)](#)  ,  
[Attribute.GetCustomAttributes\(ParameterInfo, Type, bool\)](#)  , [Attribute.GetHashCode\(\)](#)  ,  
[Attribute.IsDefaultAttribute\(\)](#)  , [Attribute.IsDefined\(Assembly, Type\)](#)  ,  
[Attribute.IsDefined\(Assembly, Type, bool\)](#)  , [Attribute.IsDefined\(MemberInfo, Type\)](#)  ,  
[Attribute.IsDefined\(MemberInfo, Type, bool\)](#)  , [Attribute.IsDefined\(Module, Type\)](#)  ,

[Attribute.IsDefined\(Module, Type, bool\)](#) , [Attribute.IsDefined\(ParameterInfo, Type\)](#) ,  
[Attribute.IsDefined\(ParameterInfo, Type, bool\)](#) , [Attribute.Match\(object\)](#) , [Attribute.TypeId](#) ,  
[object.Equals\(object, object\)](#) , [object.GetType\(\)](#) , [object.MemberwiseClone\(\)](#) ,  
[object.ReferenceEquals\(object, object\)](#) , [object.ToString\(\)](#)

## Extension Methods

[TypeConversionExtensions.RonConvert\(object, Type\)](#) ,  
[TypeConversionExtensions.RonConvert<T>\(object\)](#)

# Class RonFromAttribute

Namespace: [RonCS](#)

Assembly: RonCS.dll

Marks a method as a candidate for RonFrom conversion when Serializing or Deserializing.

```
[AttributeUsage(AttributeTargets.Method)]  
public class RonFromAttribute : Attribute
```

## Inheritance

[object](#)  ← [Attribute](#)  ← RonFromAttribute

## Inherited Members

[Attribute.Equals\(object\)](#)  , [Attribute.GetCustomAttribute\(Assembly, Type\)](#)  ,  
[Attribute.GetCustomAttribute\(Assembly, Type, bool\)](#)  ,  
[Attribute.GetCustomAttribute\(MemberInfo, Type\)](#)  ,  
[Attribute.GetCustomAttribute\(MemberInfo, Type, bool\)](#)  ,  
[Attribute.GetCustomAttribute\(Module, Type\)](#)  ,  
[Attribute.GetCustomAttribute\(Module, Type, bool\)](#)  ,  
[Attribute.GetCustomAttribute\(ParameterInfo, Type\)](#)  ,  
[Attribute.GetCustomAttribute\(ParameterInfo, Type, bool\)](#)  ,  
[Attribute.GetCustomAttributes\(Assembly\)](#)  , [Attribute.GetCustomAttributes\(Assembly, bool\)](#)  ,  
[Attribute.GetCustomAttributes\(Assembly, Type\)](#)  ,  
[Attribute.GetCustomAttributes\(Assembly, Type, bool\)](#)  ,  
[Attribute.GetCustomAttributes\(MemberInfo\)](#)  ,  
[Attribute.GetCustomAttributes\(MemberInfo, bool\)](#)  ,  
[Attribute.GetCustomAttributes\(MemberInfo, Type\)](#)  ,  
[Attribute.GetCustomAttributes\(MemberInfo, Type, bool\)](#)  ,  
[Attribute.GetCustomAttributes\(Module\)](#)  , [Attribute.GetCustomAttributes\(Module, bool\)](#)  ,  
[Attribute.GetCustomAttributes\(Module, Type\)](#)  ,  
[Attribute.GetCustomAttributes\(Module, Type, bool\)](#)  ,  
[Attribute.GetCustomAttributes\(ParameterInfo\)](#)  ,  
[Attribute.GetCustomAttributes\(ParameterInfo, bool\)](#)  ,  
[Attribute.GetCustomAttributes\(ParameterInfo, Type\)](#)  ,  
[Attribute.GetCustomAttributes\(ParameterInfo, Type, bool\)](#)  , [Attribute.GetHashCode\(\)](#)  ,  
[Attribute.IsDefaultAttribute\(\)](#)  , [Attribute.IsDefined\(Assembly, Type\)](#)  ,  
[Attribute.IsDefined\(Assembly, Type, bool\)](#)  , [Attribute.IsDefined\(MemberInfo, Type\)](#)  ,  
[Attribute.IsDefined\(MemberInfo, Type, bool\)](#)  , [Attribute.IsDefined\(Module, Type\)](#)  ,

[Attribute.IsDefined\(Module, Type, bool\)](#) , [Attribute.IsDefined\(ParameterInfo, Type\)](#) ,  
[Attribute.IsDefined\(ParameterInfo, Type, bool\)](#) , [Attribute.Match\(object\)](#) , [Attribute.TypeId](#) ,  
[object.Equals\(object, object\)](#) , [object.GetType\(\)](#) , [object.MemberwiseClone\(\)](#) ,  
[object.ReferenceEquals\(object, object\)](#) , [object.ToString\(\)](#)

## Extension Methods

[TypeConversionExtensions.RonConvert\(object, Type\)](#) ,  
[TypeConversionExtensions.RonConvert<T>\(object\)](#)

# Class RonIncludeAttribute

Namespace: [RonCS](#)

Assembly: RonCS.dll

Element should always be serialized, regardless of visibility.

```
[AttributeUsage(AttributeTargets.Property|AttributeTargets.Field)]  
public class RonIncludeAttribute : Attribute
```

## Inheritance

[object](#)  ← [Attribute](#)  ← RonIncludeAttribute

## Inherited Members

[Attribute.Equals\(object\)](#)  , [Attribute.GetCustomAttribute\(Assembly, Type\)](#)  ,  
[Attribute.GetCustomAttribute\(Assembly, Type, bool\)](#)  ,  
[Attribute.GetCustomAttribute\(MemberInfo, Type\)](#)  ,  
[Attribute.GetCustomAttribute\(MemberInfo, Type, bool\)](#)  ,  
[Attribute.GetCustomAttribute\(Module, Type\)](#)  ,  
[Attribute.GetCustomAttribute\(Module, Type, bool\)](#)  ,  
[Attribute.GetCustomAttribute\(ParameterInfo, Type\)](#)  ,  
[Attribute.GetCustomAttribute\(ParameterInfo, Type, bool\)](#)  ,  
[Attribute.GetCustomAttributes\(Assembly\)](#)  , [Attribute.GetCustomAttributes\(Assembly, bool\)](#)  ,  
[Attribute.GetCustomAttributes\(Assembly, Type\)](#)  ,  
[Attribute.GetCustomAttributes\(Assembly, Type, bool\)](#)  ,  
[Attribute.GetCustomAttributes\(MemberInfo\)](#)  ,  
[Attribute.GetCustomAttributes\(MemberInfo, bool\)](#)  ,  
[Attribute.GetCustomAttributes\(MemberInfo, Type\)](#)  ,  
[Attribute.GetCustomAttributes\(MemberInfo, Type, bool\)](#)  ,  
[Attribute.GetCustomAttributes\(Module\)](#)  , [Attribute.GetCustomAttributes\(Module, bool\)](#)  ,  
[Attribute.GetCustomAttributes\(Module, Type\)](#)  ,  
[Attribute.GetCustomAttributes\(Module, Type, bool\)](#)  ,  
[Attribute.GetCustomAttributes\(ParameterInfo\)](#)  ,  
[Attribute.GetCustomAttributes\(ParameterInfo, bool\)](#)  ,  
[Attribute.GetCustomAttributes\(ParameterInfo, Type\)](#)  ,  
[Attribute.GetCustomAttributes\(ParameterInfo, Type, bool\)](#)  , [Attribute.GetHashCode\(\)](#)  ,  
[Attribute.IsDefaultAttribute\(\)](#)  , [Attribute.IsDefined\(Assembly, Type\)](#)  ,  
[Attribute.IsDefined\(Assembly, Type, bool\)](#)  , [Attribute.IsDefined\(MemberInfo, Type\)](#)  ,  
[Attribute.IsDefined\(MemberInfo, Type, bool\)](#)  , [Attribute.IsDefined\(Module, Type\)](#)  ,

[Attribute.IsDefined\(Module, Type, bool\)](#) , [Attribute.IsDefined\(ParameterInfo, Type\)](#) ,  
[Attribute.IsDefined\(ParameterInfo, Type, bool\)](#) , [Attribute.Match\(object\)](#) , [Attribute.TypeId](#) ,  
[object.Equals\(object, object\)](#) , [object.GetType\(\)](#) , [object.MemberwiseClone\(\)](#) ,  
[object.ReferenceEquals\(object, object\)](#) , [object.ToString\(\)](#)

## Extension Methods

[TypeConversionExtensions.RonConvert\(object, Type\)](#) ,  
[TypeConversionExtensions.RonConvert<T>\(object\)](#)

# Class RonIntoAttribute

Namespace: [RonCS](#)

Assembly: RonCS.dll

Indicates that method can be used for ron auto conversion.

```
[AttributeUsage(AttributeTargets.Method)]  
public class RonIntoAttribute : Attribute
```

## Inheritance

[object](#) ← [Attribute](#) ← RonIntoAttribute

## Inherited Members

[Attribute.Equals\(object\)](#) , [Attribute.GetCustomAttribute\(Assembly, Type\)](#) ,  
[Attribute.GetCustomAttribute\(Assembly, Type, bool\)](#) ,  
[Attribute.GetCustomAttribute\(MemberInfo, Type\)](#) ,  
[Attribute.GetCustomAttribute\(MemberInfo, Type, bool\)](#) ,  
[Attribute.GetCustomAttribute\(Module, Type\)](#) ,  
[Attribute.GetCustomAttribute\(Module, Type, bool\)](#) ,  
[Attribute.GetCustomAttribute\(ParameterInfo, Type\)](#) ,  
[Attribute.GetCustomAttribute\(ParameterInfo, Type, bool\)](#) ,  
[Attribute.GetCustomAttributes\(Assembly\)](#) , [Attribute.GetCustomAttributes\(Assembly, bool\)](#) ,  
[Attribute.GetCustomAttributes\(Assembly, Type\)](#) ,  
[Attribute.GetCustomAttributes\(Assembly, Type, bool\)](#) ,  
[Attribute.GetCustomAttributes\(MemberInfo\)](#) ,  
[Attribute.GetCustomAttributes\(MemberInfo, bool\)](#) ,  
[Attribute.GetCustomAttributes\(MemberInfo, Type\)](#) ,  
[Attribute.GetCustomAttributes\(MemberInfo, Type, bool\)](#) ,  
[Attribute.GetCustomAttributes\(Module\)](#) , [Attribute.GetCustomAttributes\(Module, bool\)](#) ,  
[Attribute.GetCustomAttributes\(Module, Type\)](#) ,  
[Attribute.GetCustomAttributes\(Module, Type, bool\)](#) ,  
[Attribute.GetCustomAttributes\(ParameterInfo\)](#) ,  
[Attribute.GetCustomAttributes\(ParameterInfo, bool\)](#) ,  
[Attribute.GetCustomAttributes\(ParameterInfo, Type\)](#) ,  
[Attribute.GetCustomAttributes\(ParameterInfo, Type, bool\)](#) , [Attribute.GetHashCode\(\)](#) ,  
[Attribute.IsDefaultAttribute\(\)](#) , [Attribute.IsDefined\(Assembly, Type\)](#) ,  
[Attribute.IsDefined\(Assembly, Type, bool\)](#) , [Attribute.IsDefined\(MemberInfo, Type\)](#) ,  
[Attribute.IsDefined\(MemberInfo, Type, bool\)](#) , [Attribute.IsDefined\(Module, Type\)](#) ,

[Attribute.IsDefined\(Module, Type, bool\)](#) , [Attribute.IsDefined\(ParameterInfo, Type\)](#) ,  
[Attribute.IsDefined\(ParameterInfo, Type, bool\)](#) , [Attribute.Match\(object\)](#) , [Attribute.TypeId](#) ,  
[object.Equals\(object, object\)](#) , [object.GetType\(\)](#) , [object.MemberwiseClone\(\)](#) ,  
[object.ReferenceEquals\(object, object\)](#) , [object.ToString\(\)](#)

## Extension Methods

[TypeConversionExtensions.RonConvert\(object, Type\)](#) ,  
[TypeConversionExtensions.RonConvert<T>\(object\)](#)

# Class RonListAttribute

Namespace: [RonCS](#)

Assembly: RonCS.dll

Marks a class or field as a list.

```
[AttributeUsage(AttributeTargets.Class|AttributeTargets.Property|AttributeTargets.Field)]
```

```
public class RonListAttribute : Attribute
```

## Inheritance

[object](#)  ← [Attribute](#)  ← RonListAttribute

## Inherited Members

[Attribute.Equals\(object\)](#)  , [Attribute.GetCustomAttribute\(Assembly, Type\)](#)  ,  
[Attribute.GetCustomAttribute\(Assembly, Type, bool\)](#)  ,  
[Attribute.GetCustomAttribute\(MemberInfo, Type\)](#)  ,  
[Attribute.GetCustomAttribute\(MemberInfo, Type, bool\)](#)  ,  
[Attribute.GetCustomAttribute\(Module, Type\)](#)  ,  
[Attribute.GetCustomAttribute\(Module, Type, bool\)](#)  ,  
[Attribute.GetCustomAttribute\(ParameterInfo, Type\)](#)  ,  
[Attribute.GetCustomAttribute\(ParameterInfo, Type, bool\)](#)  ,  
[Attribute.GetCustomAttributes\(Assembly\)](#)  , [Attribute.GetCustomAttributes\(Assembly, bool\)](#)  ,  
[Attribute.GetCustomAttributes\(Assembly, Type\)](#)  ,  
[Attribute.GetCustomAttributes\(Assembly, Type, bool\)](#)  ,  
[Attribute.GetCustomAttributes\(MemberInfo\)](#)  ,  
[Attribute.GetCustomAttributes\(MemberInfo, bool\)](#)  ,  
[Attribute.GetCustomAttributes\(MemberInfo, Type\)](#)  ,  
[Attribute.GetCustomAttributes\(MemberInfo, Type, bool\)](#)  ,  
[Attribute.GetCustomAttributes\(Module\)](#)  , [Attribute.GetCustomAttributes\(Module, bool\)](#)  ,  
[Attribute.GetCustomAttributes\(Module, Type\)](#)  ,  
[Attribute.GetCustomAttributes\(Module, Type, bool\)](#)  ,  
[Attribute.GetCustomAttributes\(ParameterInfo\)](#)  ,  
[Attribute.GetCustomAttributes\(ParameterInfo, bool\)](#)  ,  
[Attribute.GetCustomAttributes\(ParameterInfo, Type\)](#)  ,  
[Attribute.GetCustomAttributes\(ParameterInfo, Type, bool\)](#)  , [Attribute.GetHashCode\(\)](#)  ,  
[Attribute.IsDefaultAttribute\(\)](#)  , [Attribute.IsDefined\(Assembly, Type\)](#)  ,  
[Attribute.IsDefined\(Assembly, Type, bool\)](#)  , [Attribute.IsDefined\(MemberInfo, Type\)](#)  ,

[Attribute.IsDefined\(MemberInfo, Type, bool\)](#) , [Attribute.IsDefined\(Module, Type\)](#) ,  
[Attribute.IsDefined\(Module, Type, bool\)](#) , [Attribute.IsDefined\(ParameterInfo, Type\)](#) ,  
[Attribute.IsDefined\(ParameterInfo, Type, bool\)](#) , [Attribute.Match\(object\)](#) , [Attribute.TypeId](#) ,  
[object.Equals\(object, object\)](#) , [object.GetType\(\)](#) , [object.MemberwiseClone\(\)](#) ,  
[object.ReferenceEquals\(object, object\)](#) , [object.ToString\(\)](#)

## Extension Methods

[TypeConversionExtensions.RonConvert\(object, Type\)](#) ,  
[TypeConversionExtensions.RonConvert<T>\(object\)](#)

# Class RonMapAttribute

Namespace: [RonCS](#)

Assembly: RonCS.dll

Marks a class or field as a ron map.

```
[AttributeUsage(AttributeTargets.Class|AttributeTargets.Property|AttributeTargets.Field)]
```

```
public class RonMapAttribute : Attribute
```

## Inheritance

[object](#)  ← [Attribute](#)  ← RonMapAttribute

## Inherited Members

[Attribute.Equals\(object\)](#)  , [Attribute.GetCustomAttribute\(Assembly, Type\)](#)  ,  
[Attribute.GetCustomAttribute\(Assembly, Type, bool\)](#)  ,  
[Attribute.GetCustomAttribute\(MemberInfo, Type\)](#)  ,  
[Attribute.GetCustomAttribute\(MemberInfo, Type, bool\)](#)  ,  
[Attribute.GetCustomAttribute\(Module, Type\)](#)  ,  
[Attribute.GetCustomAttribute\(Module, Type, bool\)](#)  ,  
[Attribute.GetCustomAttribute\(ParameterInfo, Type\)](#)  ,  
[Attribute.GetCustomAttribute\(ParameterInfo, Type, bool\)](#)  ,  
[Attribute.GetCustomAttributes\(Assembly\)](#)  , [Attribute.GetCustomAttributes\(Assembly, bool\)](#)  ,  
[Attribute.GetCustomAttributes\(Assembly, Type\)](#)  ,  
[Attribute.GetCustomAttributes\(Assembly, Type, bool\)](#)  ,  
[Attribute.GetCustomAttributes\(MemberInfo\)](#)  ,  
[Attribute.GetCustomAttributes\(MemberInfo, bool\)](#)  ,  
[Attribute.GetCustomAttributes\(MemberInfo, Type\)](#)  ,  
[Attribute.GetCustomAttributes\(MemberInfo, Type, bool\)](#)  ,  
[Attribute.GetCustomAttributes\(Module\)](#)  , [Attribute.GetCustomAttributes\(Module, bool\)](#)  ,  
[Attribute.GetCustomAttributes\(Module, Type\)](#)  ,  
[Attribute.GetCustomAttributes\(Module, Type, bool\)](#)  ,  
[Attribute.GetCustomAttributes\(ParameterInfo\)](#)  ,  
[Attribute.GetCustomAttributes\(ParameterInfo, bool\)](#)  ,  
[Attribute.GetCustomAttributes\(ParameterInfo, Type\)](#)  ,  
[Attribute.GetCustomAttributes\(ParameterInfo, Type, bool\)](#)  , [Attribute.GetHashCode\(\)](#)  ,  
[Attribute.IsDefaultAttribute\(\)](#)  , [Attribute.IsDefined\(Assembly, Type\)](#)  ,  
[Attribute.IsDefined\(Assembly, Type, bool\)](#)  , [Attribute.IsDefined\(MemberInfo, Type\)](#)  ,

[Attribute.IsDefined\(MemberInfo, Type, bool\)](#) , [Attribute.IsDefined\(Module, Type\)](#) ,  
[Attribute.IsDefined\(Module, Type, bool\)](#) , [Attribute.IsDefined\(ParameterInfo, Type\)](#) ,  
[Attribute.IsDefined\(ParameterInfo, Type, bool\)](#) , [Attribute.Match\(object\)](#) , [Attribute.TypeId](#) ,  
[object.Equals\(object, object\)](#) , [object.GetType\(\)](#) , [object.MemberwiseClone\(\)](#) ,  
[object.ReferenceEquals\(object, object\)](#) , [object.ToString\(\)](#)

## Extension Methods

[TypeConversionExtensions.RonConvert\(object, Type\)](#) ,  
[TypeConversionExtensions.RonConvert<T>\(object\)](#)

# Enum RonPrintMode

Namespace: [RonCS](#)

Assembly: RonCS.dll

The print mode to use for Ron printing.

```
public enum RonPrintMode
```

## Extension Methods

[TypeConversionExtensions.RonConvert\(object, Type\)](#) ,  
[TypeConversionExtensions.RonConvert<T>\(object\)](#)

## Fields

**Compact** = 0

The most compact ron string possible.

**Pretty** = 1

Format ron with new lines and indent.

# Class RonPrintOptions

Namespace: [RonCS](#)

Assembly: RonCS.dll

Ron print options.

```
public class RonPrintOptions
```

## Inheritance

[object](#)  ← RonPrintOptions

## Inherited Members

[object.Equals\(object\)](#)  , [object.Equals\(object, object\)](#)  , [object.GetHashCode\(\)](#)  ,  
[object.GetType\(\)](#)  , [object.MemberwiseClone\(\)](#)  , [object.ReferenceEquals\(object, object\)](#)  ,  
[object.ToString\(\)](#) 

## Extension Methods

[TypeConversionExtensions.RonConvert\(object, Type\)](#) ,  
[TypeConversionExtensions.RonConvert<T>\(object\)](#)

## Fields

### indent

The indent to use for the Ron document.

```
public string indent
```

### Field Value

[string](#) 

### mode

The mode to use for Ron printing.

```
public RonPrintMode mode
```

Field Value

[RonPrintMode](#)

## Methods

### Compact()

Create the default compact print options.

```
public static RonPrintOptions Compact()
```

Returns

[RonPrintOptions](#)

### Pretty()

Create the default pretty print options.

```
public static RonPrintOptions Pretty()
```

Returns

[RonPrintOptions](#)

# Class RonProxyAttribute

Namespace: [RonCS](#)

Assembly: RonCS.dll

Indicates that a class should be converted to or from the proxy type for serialization.

```
[AttributeUsage(AttributeTargets.Class|AttributeTargets.Property|AttributeTargets.Field)]
```

```
public class RonProxyAttribute : Attribute
```

## Inheritance

[object](#)  ← [Attribute](#)  ← RonProxyAttribute

## Inherited Members

[Attribute.Equals\(object\)](#)  , [Attribute.GetCustomAttribute\(Assembly, Type\)](#)  ,  
[Attribute.GetCustomAttribute\(Assembly, Type, bool\)](#)  ,  
[Attribute.GetCustomAttribute\(MemberInfo, Type\)](#)  ,  
[Attribute.GetCustomAttribute\(MemberInfo, Type, bool\)](#)  ,  
[Attribute.GetCustomAttribute\(Module, Type\)](#)  ,  
[Attribute.GetCustomAttribute\(Module, Type, bool\)](#)  ,  
[Attribute.GetCustomAttribute\(ParameterInfo, Type\)](#)  ,  
[Attribute.GetCustomAttribute\(ParameterInfo, Type, bool\)](#)  ,  
[Attribute.GetCustomAttributes\(Assembly\)](#)  , [Attribute.GetCustomAttributes\(Assembly, bool\)](#)  ,  
[Attribute.GetCustomAttributes\(Assembly, Type\)](#)  ,  
[Attribute.GetCustomAttributes\(Assembly, Type, bool\)](#)  ,  
[Attribute.GetCustomAttributes\(MemberInfo\)](#)  ,  
[Attribute.GetCustomAttributes\(MemberInfo, bool\)](#)  ,  
[Attribute.GetCustomAttributes\(MemberInfo, Type\)](#)  ,  
[Attribute.GetCustomAttributes\(MemberInfo, Type, bool\)](#)  ,  
[Attribute.GetCustomAttributes\(Module\)](#)  , [Attribute.GetCustomAttributes\(Module, bool\)](#)  ,  
[Attribute.GetCustomAttributes\(Module, Type\)](#)  ,  
[Attribute.GetCustomAttributes\(Module, Type, bool\)](#)  ,  
[Attribute.GetCustomAttributes\(ParameterInfo\)](#)  ,  
[Attribute.GetCustomAttributes\(ParameterInfo, bool\)](#)  ,  
[Attribute.GetCustomAttributes\(ParameterInfo, Type\)](#)  ,  
[Attribute.GetCustomAttributes\(ParameterInfo, Type, bool\)](#)  , [Attribute.GetHashCode\(\)](#)  ,  
[Attribute.IsDefaultAttribute\(\)](#)  , [Attribute.IsDefined\(Assembly, Type\)](#)  ,  
[Attribute.IsDefined\(Assembly, Type, bool\)](#)  , [Attribute.IsDefined\(MemberInfo, Type\)](#)  ,

[Attribute.IsDefined\(MemberInfo, Type, bool\)](#) , [Attribute.IsDefined\(Module, Type\)](#) ,  
[Attribute.IsDefined\(Module, Type, bool\)](#) , [Attribute.IsDefined\(ParameterInfo, Type\)](#) ,  
[Attribute.IsDefined\(ParameterInfo, Type, bool\)](#) , [Attribute.Match\(object\)](#) , [Attribute.TypeId](#) ,  
[object.Equals\(object, object\)](#) , [object.GetType\(\)](#) , [object.MemberwiseClone\(\)](#) ,  
[object.ReferenceEquals\(object, object\)](#) , [object.ToString\(\)](#)

## Extension Methods

[TypeConversionExtensions.RonConvert\(object, Type\)](#) ,  
[TypeConversionExtensions.RonConvert<T>\(object\)](#)

# Constructors

## RonProxyAttribute(Type)

Indicates that a class should be converted to or from the proxy type for serialization.

```
public RonProxyAttribute(Type proxy)
```

## Parameters

proxy [Type](#)

# Fields

## Proxy

The type that provides the proxy for this type.

```
public readonly Type Proxy
```

## Field Value

[Type](#)

# Class RonTupleAttribute

Namespace: [RonCS](#)

Assembly: RonCS.dll

Marks a method that should be used to serialize the element as a ron tuple.

```
[AttributeUsage(AttributeTargets.Method|AttributeTargets.Property)]  
public class RonTupleAttribute : Attribute
```

## Inheritance

[object](#)  ← [Attribute](#)  ← RonTupleAttribute

## Inherited Members

[Attribute.Equals\(object\)](#)  , [Attribute.GetCustomAttribute\(Assembly, Type\)](#)  ,  
[Attribute.GetCustomAttribute\(Assembly, Type, bool\)](#)  ,  
[Attribute.GetCustomAttribute\(MemberInfo, Type\)](#)  ,  
[Attribute.GetCustomAttribute\(MemberInfo, Type, bool\)](#)  ,  
[Attribute.GetCustomAttribute\(Module, Type\)](#)  ,  
[Attribute.GetCustomAttribute\(Module, Type, bool\)](#)  ,  
[Attribute.GetCustomAttribute\(ParameterInfo, Type\)](#)  ,  
[Attribute.GetCustomAttribute\(ParameterInfo, Type, bool\)](#)  ,  
[Attribute.GetCustomAttributes\(Assembly\)](#)  , [Attribute.GetCustomAttributes\(Assembly, bool\)](#)  ,  
[Attribute.GetCustomAttributes\(Assembly, Type\)](#)  ,  
[Attribute.GetCustomAttributes\(Assembly, Type, bool\)](#)  ,  
[Attribute.GetCustomAttributes\(MemberInfo\)](#)  ,  
[Attribute.GetCustomAttributes\(MemberInfo, bool\)](#)  ,  
[Attribute.GetCustomAttributes\(MemberInfo, Type\)](#)  ,  
[Attribute.GetCustomAttributes\(MemberInfo, Type, bool\)](#)  ,  
[Attribute.GetCustomAttributes\(Module\)](#)  , [Attribute.GetCustomAttributes\(Module, bool\)](#)  ,  
[Attribute.GetCustomAttributes\(Module, Type\)](#)  ,  
[Attribute.GetCustomAttributes\(Module, Type, bool\)](#)  ,  
[Attribute.GetCustomAttributes\(ParameterInfo\)](#)  ,  
[Attribute.GetCustomAttributes\(ParameterInfo, bool\)](#)  ,  
[Attribute.GetCustomAttributes\(ParameterInfo, Type\)](#)  ,  
[Attribute.GetCustomAttributes\(ParameterInfo, Type, bool\)](#)  , [Attribute.GetHashCode\(\)](#)  ,  
[Attribute.IsDefaultAttribute\(\)](#)  , [Attribute.IsDefined\(Assembly, Type\)](#)  ,  
[Attribute.IsDefined\(Assembly, Type, bool\)](#)  , [Attribute.IsDefined\(MemberInfo, Type\)](#)  ,  
[Attribute.IsDefined\(MemberInfo, Type, bool\)](#)  , [Attribute.IsDefined\(Module, Type\)](#)  ,

[Attribute.IsDefined\(Module, Type, bool\)](#) , [Attribute.IsDefined\(ParameterInfo, Type\)](#) ,  
[Attribute.IsDefined\(ParameterInfo, Type, bool\)](#) , [Attribute.Match\(object\)](#) , [Attribute.TypeId](#) ,  
[object.Equals\(object, object\)](#) , [object.GetType\(\)](#) , [object.MemberwiseClone\(\)](#) ,  
[object.ReferenceEquals\(object, object\)](#) , [object.ToString\(\)](#)

## Extension Methods

[TypeConversionExtensions.RonConvert\(object, Type\)](#) ,  
[TypeConversionExtensions.RonConvert<T>\(object\)](#)

# Class SerializationContext

Namespace: [RonCS](#)

Assembly: RonCS.dll

Context for serializing ron elements. Custom overrides for Ron are stored in the local or global serialization context.

```
public class SerializationContext
```

## Inheritance

[object](#)  ← [SerializationContext](#)

## Inherited Members

[object.Equals\(object\)](#)  , [object.Equals\(object, object\)](#)  , [object.GetHashCode\(\)](#)  ,  
[object.GetType\(\)](#)  , [object.MemberwiseClone\(\)](#)  , [object.ReferenceEquals\(object, object\)](#)  ,  
[object.ToString\(\)](#) 

## Extension Methods

[TypeConversionExtensions.RonConvert\(object, Type\)](#) ,  
[TypeConversionExtensions.RonConvert<T>\(object\)](#)

## Constructors

### SerializationContext(SerializationContext?)

Context for serializing ron elements. Custom overrides for Ron are stored in the local or global serialization context.

```
public SerializationContext(SerializationContext? parentContext = null)
```

## Parameters

**parentContext** [SerializationContext](#)

## Fields

# RonTypes

Set of types recognized by this serialization context.

```
public readonly HashSet<Type> RonTypes
```

Field Value

[HashSet](#) <[Type](#)>

## proxyTypes

Proxy types recognized by this serialization context.

```
public readonly Dictionary<Type, Type> proxyTypes
```

Field Value

[Dictionary](#) <[Type](#), [Type](#)>

## Methods

### ConvertType(object?, Type?)

Convert type from the source to the targetType.

```
public object? ConvertType(object? source, Type? targetType)
```

Parameters

source [object](#)

targetType [Type](#)

Returns

[object](#)

## GetIntermediateType(Type?)

Get intermediate deserialization type, such as for a proxy.

```
public Type? GetIntermediateType(Type? targetType)
```

### Parameters

**targetType** [Type](#)

### Returns

[Type](#)

## GetMapIntermediateType(Type?)

Get the value type for deserializing a ron map.

```
public Type? GetMapIntermediateType(Type? type)
```

### Parameters

**type** [Type](#)

### Returns

[Type](#)

## GetTypeFromName(string?, Type?)

Get a type from it's name.

```
public Type? GetTypeFromName(string? name, Type? backupType)
```

### Parameters

**name** [string](#)

backupType [Type](#)

Returns

[Type](#)

Exceptions

[InvalidOperationException](#)

## InferType(RonElement?)

Infer the type of the AST element. If the type cannot be inferred then return null.

```
public Type? InferType(RonElement? element)
```

Parameters

element [RonElement](#)

Returns

[Type](#)

Exceptions

[NotImplementedException](#)

## RegisterListType(Type)

Register type to be serialized as a list.

```
public void RegisterListType(Type type)
```

Parameters

type [Type](#)

## RegisterMapType(Type)

Register type to be serialized as a map.

```
public void RegisterMapType(Type type)
```

### Parameters

type [Type](#)

## RegisterProxyType(Type, Type)

Register a custom proxy for the source type.

```
public void RegisterProxyType(Type sourceType, Type proxyType)
```

### Parameters

sourceType [Type](#)

proxyType [Type](#)

## RegisterTupleConverter<T>(Func<T, object[]>)

Register converter to serialize a type as a tuple.

```
public void RegisterTupleConverter<T>(Func<T, object[]> converter)
```

### Parameters

converter [Func](#)<T, [object](#)[]>

### Type Parameters

T

## RegisterType(Type)

Register a new known type

```
public void RegisterType(Type type)
```

### Parameters

type [Type](#)

## RegisterTypeConverter(Type, TypeSerializerConverter)

Register a custom type converter for the type.

```
public void RegisterTypeConverter(Type type, TypeSerializerConverter converter)
```

### Parameters

type [Type](#)

converter [TypeSerializerConverter](#)

## ToAST(object?, Type?)

Convert the object to a Ron AST. If field type is provided it will allow for inference for the element.

```
public RonElement ToAST(object? source, Type? fieldType = null)
```

### Parameters

source [object](#)

fieldType [Type](#)

### Returns

[RonElement](#)



# Class TypeConversionExtensions

Namespace: [RonCS](#)

Assembly: RonCS.dll

Extension methods for converting ron objects.

```
public static class TypeConversionExtensions
```

## Inheritance

[object](#)  ← TypeConversionExtensions

## Inherited Members

[object.Equals\(object\)](#)  , [object.Equals\(object, object\)](#)  , [object.GetHashCode\(\)](#)  ,  
[object.GetType\(\)](#)  , [object.MemberwiseClone\(\)](#)  , [object.ReferenceEquals\(object, object\)](#)  ,  
[object.ToString\(\)](#) 

## Methods

### RonConvert(object, Type)

Use the RonConvert algorithm to convert the element to the type T.

```
public static object RonConvert(this object source, Type targetType)
```

## Parameters

source [object](#) 

targetType [Type](#) 

## Returns

[object](#) 

### RonConvert<T>(object)

Use the RonConvert algorithm to convert the element to the type T.

```
public static T RonConvert<T>(this object source)
```

## Parameters

source [object](#)

## Returns

T

## Type Parameters

T

# Interface TypeSerializerConverter

Namespace: [RonCS](#)

Assembly: RonCS.dll

Base interface for serialization converters. Serialization converters convert C# objects into Ron AST nodes.

```
public interface TypeSerializerConverter
```

## Extension Methods

[TypeConversionExtensions.RonConvert\(object, Type\)](#) ,  
[TypeConversionExtensions.RonConvert<T>\(object\)](#)

## Methods

### CreateTypeConverterForDictionary(Type)

Create a type converter for a dictionary type.

```
public static TypeSerializerConverter? CreateTypeConverterForDictionary(Type type)
```

## Parameters

type [Type](#)<sup>↗</sup>

## Returns

[TypeSerializerConverter](#)

### CreateTypeConverterForList(Type)

Create type converter for a list type if possible. Return null otherwise.

```
public static TypeSerializerConverter? CreateTypeConverterForList(Type type)
```

## Parameters

type [Type](#) 

## Returns

[TypeSerializerConverter](#)

# CreateTypeConverterForObjectType(Type)

Create type converter for an object type.

```
public static TypeSerializerConverter CreateTypeConverterForObjectType(Type type)
```

## Parameters

type [Type](#) 

## Returns

[TypeSerializerConverter](#)

# CreateTypeConverterForTypeWithFields(Type, string?)

Create type converter for a type that has fields.

```
public static TypeSerializerConverter CreateTypeConverterForTypeWithFields(Type  
type, string? typeName)
```

## Parameters

type [Type](#) 

typeName [string](#) 

## Returns

[TypeSerializerConverter](#)

## CreateTypeConverterFromTypeAttrs(Type)

Create a type converter from attributes if possible. If no type converter can be created return null.

```
public static TypeSerializerConverter? CreateTypeConverterFromTypeAttrs(Type type)
```

### Parameters

type [Type](#)<sup>↗</sup>

### Returns

[TypeSerializerConverter](#)

## ToAST(SerializationContext, object)

Convert the source object to an AST node.

```
RonElement ToAST(SerializationContext context, object source)
```

### Parameters

context [SerializationContext](#)

source [object](#)<sup>↗</sup>

### Returns

[RonElement](#)

# Namespace RonCS.AST

## Classes

### [NumberParser](#)

Ron parser for numbers.

### [RonAsciiEscape](#)

AST element for an ascii escape character.

### [RonAsciiLiteral](#)

AST element for an ascii literal character.

### [RonBool](#)

AST element for a RonBool

### [RonBuilder](#)

Builder for RON AST's

### [RonByte](#)

AST element for a byte value.

### [RonByteEscape](#)

AST element for a byte escape character.

### [RonChar](#)

AST element for a RonChar.

### [RonDocument](#)

AST element for a ron document.

### [RonElement](#)

Parent class for a ron element.

### [RonElementExtensions](#)

Ron element extensions.

### [RonExponent](#)

AST element for a float exponent.

### [RonFloat](#)

AST element representing a float value.

### [RonFloatNumber](#)

Base class for differentiating standard and special float numbers.

### [RonIdentifier](#)

AST element for a ron identifier.

### [RonInteger](#)

AST element for an integer value.

### [RonLexer](#)

Base class for ron tokenizer

### [RonList](#)

AST element for a ron list.

### [RonMap](#)

AST element for a Ron map

### [RonMapItem](#)

AST element for an element in a ron map. In most cases key should be a ron string.

### [RonMapStruct](#)

AST element for a ron map struct.

### [RonNamedValue](#)

AST element for a ron named value. These are typically body elements for a ron struct.

### [RonNamedValueStruct](#)

AST element for a ron struct with named values.

### [RonNone](#)

AST element representing a ron none.

### [RonParser](#)

Parser for ron documents

### [RonRange](#)

AST element for a Ron range.

### [RonRawIdentifier](#)

AST element for a raw identifier.

### [RonSome](#)

AST element for a ron some.

### [RonSpecialFloat](#)

AST element for a special float number.

### [RonStandardFloat](#)

AST element representing a standard float number.

### [RonString](#)

AST element representing a string.

### [RonStringLit](#)

Literal string content.

### [RonStringRawContent](#)

Raw string.

### [RonStringRawLit](#)

Raw string literal.

### [RonStruct](#)

Base class for struct AST elements.

### [RonTuple](#)

AST element for a Ron tuple.

### [RonTupleStruct](#)

AST element for a struct with a tuple body.

### [RonUnicodeEscape](#)

Unicode escape content.

### [RonUnitStruct](#)

AST element for a ron Unit struct with no body.

### [RonUnsigned](#)

Unsigned integer value.

### [StringParser](#)

Parser for Ron strings.

## Interfaces

### [INumberValue](#)

Common interface for all number AST nodes.

### [StringContent](#)

Represents part of a string.

## Enums

### [FloatSuffix](#)

The suffix of a float, indicating the bit size.

### [IntegerSuffix](#)

Suffix for an integer, indicating the bit width and sign.

### [RonRangeOperator](#)

The ron element operator.

### [RonTokenKind](#)

Tokens for the RON language.

### [SpecialFloatType](#)

Type of a special float.

### [UnsignedPrefix](#)

Prefix for unsigned number, indicating the base.

# Enum FloatSuffix

Namespace: [RonCS.AST](#)

Assembly: RonCS.dll

The suffix of a float, indicating the bit size.

```
public enum FloatSuffix
```

## Extension Methods

[TypeConversionExtensions.RonConvert\(object, Type\)](#) ,  
[TypeConversionExtensions.RonConvert<T>\(object\)](#)

## Fields

f32 = 0

32 bit floating point number

f64 = 1

64 bit floating point number.

# Interface INumberValue

Namespace: [RonCS.AST](#)

Assembly: RonCS.dll

Common interface for all number AST nodes.

```
public interface INumberValue
```

## Extension Methods

[TypeConversionExtensions.RonConvert\(object, Type\)](#) ,  
[TypeConversionExtensions.RonConvert<T>\(object\)](#)

## Methods

### EvaluateNumber(Type?)

Convert the value to a number.

```
object EvaluateNumber(Type? hint)
```

#### Parameters

hint [Type](#) 

#### Returns

[object](#) 

### ValueString()

String representing the value of the number. Used for C# type conversion.

```
string ValueString()
```

#### Returns



# Enum IntegerSuffix

Namespace: [RonCS.AST](#)

Assembly: RonCS.dll

Suffix for an integer, indicating the bit width and sign.

```
public enum IntegerSuffix
```

## Extension Methods

[TypeConversionExtensions.RonConvert\(object, Type\)](#) ,  
[TypeConversionExtensions.RonConvert<T>\(object\)](#)

## Fields

i128 = 4

Signed 128 bit integer

i16 = 1

Signed 16 bit integer

i32 = 2

Signed 32 bit integer

i64 = 3

Signed 64 bit integer

i8 = 0

Signed 8 bit integer

u128 = 9

Unsigned 128 bit integer

u16 = 6

Unsigned 16 bit integer

u32 = 7

Unsigned 32 bit integer

u64 = 8

Unsigned 64 bit integer

u8 = 5

Unsigned 8 bit integer

# Class NumberParser

Namespace: [RonCS.AST](#)

Assembly: RonCS.dll

Ron parser for numbers.

```
public static class NumberParser
```

## Inheritance

[object](#)  ← NumberParser

## Inherited Members

[object.Equals\(object\)](#)  , [object.Equals\(object, object\)](#)  , [object.GetHashCode\(\)](#)  ,  
[object.GetType\(\)](#)  , [object.MemberwiseClone\(\)](#)  , [object.ReferenceEquals\(object, object\)](#)  ,  
[object.ToString\(\)](#) 

## Fields

### ByteAscii\_Parser

Escaped ascii number

```
public static TextParser<RonByte> ByteAscii_Parser
```

## Field Value

TextParser<[RonByte](#)>

### ByteContent\_Parser

Byte

```
public static TextParser<RonByte> ByteContent_Parser
```

## Field Value

TextParser<[RonByte](#)>

## Byte\_Parser

Byte

```
public static TextParser<RonByte> Byte_Parser
```

Field Value

TextParser<[RonByte](#)>

## EscapedByte\_Parser

Escaped byte

```
public static TextParser<RonByte> EscapedByte_Parser
```

Field Value

TextParser<[RonByte](#)>

## FloatExp\_Parser

Exponent

```
public static TextParser<RonExponent> FloatExp_Parser
```

Field Value

TextParser<[RonExponent](#)>

## FloatFrac\_Parser

?

```
public static TextParser<string> FloatFrac_Parser
```

Field Value

TextParser<[string](#)>

## FloatInt\_Parser

Decimal digits portion of a floating point number, excluding the decimal.

```
public static TextParser<string> FloatInt_Parser
```

Field Value

TextParser<[string](#)>

## FloatNum\_Parser

Float number part

```
public static TextParser<RonFloatNumber> FloatNum_Parser
```

Field Value

TextParser<[RonFloatNumber](#)>

## FloatStd\_Parser

Standard float.

```
public static TextParser<string> FloatStd_Parser
```

Field Value

TextParser<[string](#)>

# Float\_Parser

Float

```
public static TextParser<RonFloat> Float_Parser
```

Field Value

TextParser<[RonFloat](#)>

# IntegerSuffix\_Parser

Unsigned integer number.

```
public static TextParser<IntegerSuffix> IntegerSuffix_Parser
```

Field Value

TextParser<[IntegerSuffix](#)>

# Integer\_Parser

Integer

```
public static TextParser<RonInteger> Integer_Parser
```

Field Value

TextParser<[RonInteger](#)>

# Number\_Parser

Number

```
public static TextParser<INumberValue> Number_Parser
```

Field Value

TextParser<[INumberValue](#)>

## SpecialFloatNum\_Parser

Special float num

```
public static TextParser<RonFloatNumber> SpecialFloatNum_Parser
```

Field Value

TextParser<[RonFloatNumber](#)>

## StandardFloatNum\_Parser

Standard float num

```
public static TextParser<RonFloatNumber> StandardFloatNum_Parser
```

Field Value

TextParser<[RonFloatNumber](#)>

## UnsignedBinary\_Parser

Unsigned binary number

```
public static TextParser<RonUnsigned> UnsignedBinary_Parser
```

Field Value

TextParser<[RonUnsigned](#)>

## UnsignedDecimal\_Parser

Unsigned decimal number

```
public static TextParser<RonUnsigned> UnsignedDecimal_Parser
```

Field Value

TextParser<[RonUnsigned](#)>

## UnsignedHex\_Parser

Unsigned hex number

```
public static TextParser<RonUnsigned> UnsignedHex_Parser
```

Field Value

TextParser<[RonUnsigned](#)>

## UnsignedOctal\_Parser

Unsigned octal number

```
public static TextParser<RonUnsigned> UnsignedOctal_Parser
```

Field Value

TextParser<[RonUnsigned](#)>

## Unsigned\_Parser

Unsigned number

```
public static TextParser<RonUnsigned> Unsigned_Parser
```

Field Value

TextParser<[RonUnsigned](#)>

# Class RonAsciiEscape

Namespace: [RonCS.AST](#)

Assembly: RonCS.dll

AST element for an ascii escape character.

```
public class RonAsciiEscape : StringContent, INumberValue
```

## Inheritance

[object](#)  ← RonAsciiEscape

## Implements

[StringContent](#), [INumberValue](#)

## Inherited Members

[object.Equals\(object\)](#)  , [object.Equals\(object, object\)](#)  , [object.GetHashCode\(\)](#)  ,  
[object.GetType\(\)](#)  , [object.MemberwiseClone\(\)](#)  , [object.ReferenceEquals\(object, object\)](#)  ,  
[object.ToString\(\)](#) 

## Extension Methods

[TypeConversionExtensions.RonConvert\(object, Type\)](#) ,  
[TypeConversionExtensions.RonConvert<T>\(object\)](#)

# Constructors

## RonAsciiEscape(char)

AST element for an ascii escape character.

```
public RonAsciiEscape(char source)
```

## Parameters

source [char](#) 

# Fields

## source

The source code for the ascii character.

```
public char? source
```

## Field Value

[char](#)?

## Methods

### EvaluateNumber(Type?)

Convert the value to a number.

```
public object EvaluateNumber(Type? hint)
```

## Parameters

hint [Type](#)

## Returns

[object](#)

### EvaluateString()

Evaluate the element as a C# string.

```
public string EvaluateString()
```

## Returns

[string](#)

## Serialize()

Convert the element to a RON string.

```
public string Serialize()
```

Returns

[string](#) 

## ValueString()

String representing the value of the number. Used for C# type conversion.

```
public string ValueString()
```

Returns

[string](#) 

# Class RonAsciiLiteral

Namespace: [RonCS.AST](#)

Assembly: RonCS.dll

AST element for an ascii literal character.

```
public class RonAsciiLiteral : INumberValue
```

## Inheritance

[object](#)  ← RonAsciiLiteral

## Implements

[INumberValue](#)

## Inherited Members

[object.Equals\(object\)](#)  , [object.Equals\(object, object\)](#)  , [object.GetHashCode\(\)](#)  ,  
[object.GetType\(\)](#)  , [object.MemberwiseClone\(\)](#)  , [object.ReferenceEquals\(object, object\)](#)  ,  
[object.ToString\(\)](#) 

## Extension Methods

[TypeConversionExtensions.RonConvert\(object, Type\)](#) ,  
[TypeConversionExtensions.RonConvert<T>\(object\)](#)

# Constructors

## RonAsciiLiteral(char)

AST element for an ascii literal character.

```
public RonAsciiLiteral(char c)
```

## Parameters

c [char](#) 

# Methods

# EvaluateNumber(Type?)

Convert the value to a number.

```
public object EvaluateNumber(Type? hint)
```

## Parameters

hint [Type](#)

## Returns

[object](#)

# ValueString()

String representing the value of the number. Used for C# type conversion.

```
public string ValueString()
```

## Returns

[string](#)

# Class RonBool

Namespace: [RonCS.AST](#)

Assembly: RonCS.dll

AST element for a RonBool

```
[Serializable]  
public class RonBool : RonElement
```

## Inheritance

[object](#)  ← [RonElement](#)  ← RonBool

## Inherited Members

[object.Equals\(object\)](#)  , [object.Equals\(object, object\)](#)  , [object.GetHashCode\(\)](#)  ,  
[object.GetType\(\)](#)  , [object.MemberwiseClone\(\)](#)  , [object.ReferenceEquals\(object, object\)](#)  ,  
[object.ToString\(\)](#) 

## Extension Methods

[RonElementExtensions.IdentifierName\(RonElement?\)](#) ,  
[TypeConversionExtensions.RonConvert\(object, Type\)](#) ,  
[TypeConversionExtensions.RonConvert<T>\(object\)](#)

# Constructors

## RonBool(bool)

AST element for a RonBool

```
public RonBool(bool value = false)
```

## Parameters

value [bool](#) 

# Fields

# Value

The value of the boolean.

```
public bool Value
```

## Field Value

[bool](#)

# Methods

## RonPrint(RonPrintOptions)

Print the ron element as a Ron string.

```
public override string RonPrint(RonPrintOptions options)
```

## Parameters

**options** [RonPrintOptions](#)

## Returns

[string](#)

# Class RonBuilder

Namespace: [RonCS.AST](#)

Assembly: RonCS.dll

Builder for RON AST's

```
public static class RonBuilder
```

## Inheritance

[object](#)  ← RonBuilder

## Inherited Members

[object.Equals\(object\)](#) , [object.Equals\(object, object\)](#) , [object.GetHashCode\(\)](#) ,  
[object.GetType\(\)](#) , [object.MemberwiseClone\(\)](#) , [object.ReferenceEquals\(object, object\)](#) ,  
[object.ToString\(\)](#) 

# Properties

## None

A Ron None.

```
public static RonNone None { get; }
```

## Property Value

[RonNone](#)

# Methods

## Bool(bool)

Create a ron boolean with the specified value.

```
public static RonBool Bool(bool value)
```

## Parameters

value [bool](#) 

## Returns

[RonBool](#)

# Doc(RonElement)

Create a document with the specified element.

```
public static RonDocument Doc(RonElement value)
```

## Parameters

value [RonElement](#)

## Returns

[RonDocument](#)

# Ident(string)

Create an identifier with the specified name

```
public static RonIdentifier Ident(string name)
```

## Parameters

name [string](#) 

## Returns

[RonIdentifier](#)

## List(params RonElement[])

Create a list with the specified values.

```
public static RonList List(params RonElement[] values)
```

### Parameters

values [RonElement\[\]](#)

### Returns

[RonList](#)

## Map(params RonElement[])

Create a map with the specified values.

```
public static RonMap Map(params RonElement[] values)
```

### Parameters

values [RonElement\[\]](#)

### Returns

[RonMap](#)

## MapItem(RonElement, RonElement)

Create a map item with the specified key and value. Typically the key should be a string.

```
public static RonMapItem MapItem(RonElement key, RonElement value)
```

### Parameters

key [RonElement](#)

value [RonElement](#)

Returns

[RonMapItem](#)

## NamedValue(RonElement, RonElement)

Create a name value with a specified name and value.

```
public static RonNamedValue NamedValue(RonElement name, RonElement value)
```

Parameters

name [RonElement](#)

value [RonElement](#)

Returns

[RonNamedValue](#)

## NamedValue(string, RonElement)

Create a named value with the specified name and value.

```
public static RonNamedValue NamedValue(string name, RonElement value)
```

Parameters

name [string](#)[↗](#)

value [RonElement](#)

Returns

[RonNamedValue](#)

## NamedValueStruct(string, params RonElement[])

Create a named value struct with the specified name, and body.

```
public static RonNamedValueStruct NamedValueStruct(string name, params  
RonElement[] body)
```

### Parameters

name [string](#) 

body [RonElement\[\]](#)

### Returns

[RonNamedValueStruct](#)

## Range(RonElement?, RonRangeOperator, RonElement?)

Create a range with the specified values.

```
public static RonRange Range(RonElement? left, RonRangeOperator op,  
RonElement? right)
```

### Parameters

left [RonElement](#)

op [RonRangeOperator](#)

right [RonElement](#)

### Returns

[RonRange](#)

## RawIdent(string)

Create a raw identifier with the specified name

```
public static RonRawIdentifier RawIdent(string name)
```

## Parameters

name [string](#) 

## Returns

[RonRawIdentifier](#)

# Some(RonElement)

Create a some value

```
public static RonSome Some(RonElement value)
```

## Parameters

value [RonElement](#)

## Returns

[RonSome](#)

# Tuple(params RonElement[])

Create a tuple with the specified child values

```
public static RonTuple Tuple(params RonElement[] values)
```

## Parameters

values [RonElement\[\]](#)

## Returns

[RonTuple](#)

## TupleStruct(string, params RonElement[])

Create a tuple struct with the specified name and elements.

```
public static RonTupleStruct TupleStruct(string name, params RonElement[] body)
```

### Parameters

name [string](#) 

body [RonElement\[\]](#)

### Returns

[RonTupleStruct](#)

## UnitStruct(string)

Create a struct with a name and no body.

```
public static RonUnitStruct UnitStruct(string name)
```

### Parameters

name [string](#) 

### Returns

[RonUnitStruct](#)

# Class RonByte

Namespace: [RonCS.AST](#)

Assembly: RonCS.dll

AST element for a byte value.

```
public class RonByte : RonElement, INumberValue
```

## Inheritance

[object](#)  ← [RonElement](#) ← RonByte

## Implements

[INumberValue](#)

## Inherited Members

[object.Equals\(object\)](#)  , [object.Equals\(object, object\)](#)  , [object.GetHashCode\(\)](#)  ,  
[object.GetType\(\)](#)  , [object.MemberwiseClone\(\)](#)  , [object.ReferenceEquals\(object, object\)](#)  ,  
[object.ToString\(\)](#) 

## Extension Methods

[RonElementExtensions.IdentifierName\(RonElement?\)](#) ,  
[TypeConversionExtensions.RonConvert\(object, Type\)](#) ,  
[TypeConversionExtensions.RonConvert<T>\(object\)](#)

# Constructors

## RonByte(INumberValue)

AST element for a byte value.

```
public RonByte(INumberValue inner)
```

## Parameters

**inner** [INumberValue](#)

# Fields

## inner

The inner value of the byte.

```
public INumberValue inner
```

## Field Value

[INumberValue](#)

# Methods

## EvaluateNumber(Type?)

Convert the value to a number.

```
public object EvaluateNumber(Type? hint)
```

## Parameters

hint [Type](#)

## Returns

[object](#)

## RonPrint(RonPrintOptions)

Print the ron element as a Ron string.

```
public override string RonPrint(RonPrintOptions options)
```

## Parameters

options [RonPrintOptions](#)

Returns

[string](#) 

## ValueString()

String representing the value of the number. Used for C# type conversion.

```
public string ValueString()
```

Returns

[string](#) 

# Class RonByteEscape

Namespace: [RonCS.AST](#)

Assembly: RonCS.dll

AST element for a byte escape character.

```
public class RonByteEscape : StringContent, INumberValue
```

## Inheritance

[object](#)  ← RonByteEscape

## Implements

[StringContent](#), [INumberValue](#)

## Inherited Members

[object.Equals\(object\)](#)  , [object.Equals\(object, object\)](#)  , [object.GetHashCode\(\)](#)  ,  
[object.GetType\(\)](#)  , [object.MemberwiseClone\(\)](#)  , [object.ReferenceEquals\(object, object\)](#)  ,  
[object.ToString\(\)](#) 

## Extension Methods

[TypeConversionExtensions.RonConvert\(object, Type\)](#) ,  
[TypeConversionExtensions.RonConvert<T>\(object\)](#)

# Constructors

## RonByteEscape(char, char)

AST element for a byte escape character.

```
public RonByteEscape(char left, char right)
```

## Parameters

left [char](#) 

right [char](#) 

# Fields

## left

The left portion of the byte.

```
public char? left
```

## Field Value

[char](#)?

## right

The right portion of the byte.

```
public char? right
```

## Field Value

[char](#)?

# Methods

## EvaluateNumber(Type?)

Convert the value to a number.

```
public object EvaluateNumber(Type? hint)
```

## Parameters

hint [Type](#)

## Returns

[object](#)

## EvaluateString()

Evaluate the element as a C# string.

```
public string EvaluateString()
```

Returns

[string](#) 

## Serialize()

Convert the element to a RON string.

```
public string Serialize()
```

Returns

[string](#) 

## ValueString()

String representing the value of the number. Used for C# type conversion.

```
public string ValueString()
```

Returns

[string](#) 

# Class RonChar

Namespace: [RonCS.AST](#)

Assembly: RonCS.dll

AST element for a RonChar.

```
public class RonChar : RonElement
```

## Inheritance

[object](#)  ← [RonElement](#)  ← RonChar

## Inherited Members

[object.Equals\(object\)](#) , [object.Equals\(object, object\)](#) , [object.GetHashCode\(\)](#) ,  
[object.GetType\(\)](#) , [object.MemberwiseClone\(\)](#) , [object.ReferenceEquals\(object, object\)](#) ,  
[object.ToString\(\)](#) 

## Extension Methods

[RonElementExtensions.IdentifierName\(RonElement?\)](#),  
[TypeConversionExtensions.RonConvert\(object, Type\)](#),  
[TypeConversionExtensions.RonConvert<T>\(object\)](#)

## Constructors

### RonChar(char)

AST element for a RonChar.

```
public RonChar(char value)
```

## Parameters

value [char](#) 

## Fields

# Value

The value of the character.

```
public char Value
```

## Field Value

[char](#)

# Methods

## RonPrint(RonPrintOptions)

Print the ron element as a Ron string.

```
public override string RonPrint(RonPrintOptions options)
```

## Parameters

**options** [RonPrintOptions](#)

## Returns

[string](#)

# Class RonDocument

Namespace: [RonCS.AST](#)

Assembly: RonCS.dll

AST element for a ron document.

[Serializable]

```
public class RonDocument : RonElement
```

## Inheritance

[object](#)  ← [RonElement](#)  ← RonDocument

## Inherited Members

[object.Equals\(object\)](#) , [object.Equals\(object, object\)](#) , [object.GetHashCode\(\)](#) ,  
[object.GetType\(\)](#) , [object.MemberwiseClone\(\)](#) , [object.ReferenceEquals\(object, object\)](#) ,  
[object.ToString\(\)](#) 

## Extension Methods

[RonElementExtensions.IdentifierName\(RonElement?\)](#) ,  
[TypeConversionExtensions.RonConvert\(object, Type\)](#) ,  
[TypeConversionExtensions.RonConvert<T>\(object\)](#) 

# Constructors

## RonDocument(RonElement?)

AST element for a ron document.

```
public RonDocument(RonElement? value)
```

## Parameters

value [RonElement](#)

# Fields

# Value

The value of the document body

```
public RonElement? Value
```

## Field Value

[RonElement](#)

# Methods

## RonPrint(RonPrintOptions)

Print the ron element as a Ron string.

```
public override string RonPrint(RonPrintOptions options)
```

## Parameters

**options** [RonPrintOptions](#)

## Returns

[string](#) 

# Class RonElement

Namespace: [RonCS.AST](#)

Assembly: RonCS.dll

Parent class for a ron element.

```
[Serializable]  
public abstract class RonElement
```

## Inheritance

[object](#)  ← RonElement

## Derived

[RonBool](#), [RonByte](#), [RonChar](#), [RonDocument](#), [RonFloat](#), [RonIdentifier](#), [RonInteger](#), [RonList](#), [RonMap](#), [RonMapItem](#), [RonNamedValue](#), [RonNone](#), [RonRange](#), [RonRawIdentifier](#), [RonSome](#), [RonString](#), [RonStruct](#), [RonTuple](#)

## Inherited Members

[object.Equals\(object\)](#)  , [object.Equals\(object, object\)](#)  , [object.GetHashCode\(\)](#)  , [object.GetType\(\)](#)  , [object.MemberwiseClone\(\)](#)  , [object.ReferenceEquals\(object, object\)](#)  , [object.ToString\(\)](#) 

## Extension Methods

[RonElementExtensions.IdentifierName\(RonElement?\)](#) , [TypeConversionExtensions.RonConvert\(object, Type\)](#) , [TypeConversionExtensions.RonConvert<T>\(object\)](#)

# Methods

## RonPrint(RonPrintOptions)

Print the ron element as a Ron string.

```
public abstract string RonPrint(RonPrintOptions options)
```

## Parameters

options [RonPrintOptions](#)

Returns

[string](#) 

# Class RonElementExtensions

Namespace: [RonCS.AST](#)

Assembly: RonCS.dll

Ron element extensions.

```
public static class RonElementExtensions
```

## Inheritance

[object](#)  ← RonElementExtensions

## Inherited Members

[object.Equals\(object\)](#)  , [object.Equals\(object, object\)](#)  , [object.GetHashCode\(\)](#)  ,  
[object.GetType\(\)](#)  , [object.MemberwiseClone\(\)](#)  , [object.ReferenceEquals\(object, object\)](#)  ,  
[object.ToString\(\)](#) 

## Methods

### IdentifierName(RonElement?)

If the element is an identifier return it's name. Otherwise returns null.

```
public static string? IdentifierName(this RonElement? element)
```

## Parameters

element [RonElement](#)

## Returns

[string](#) 

# Class RonExponent

Namespace: [RonCS.AST](#)

Assembly: RonCS.dll

AST element for a float exponent.

```
public class RonExponent
```

## Inheritance

[object](#)  ← RonExponent

## Inherited Members

[object.Equals\(object\)](#)  , [object.Equals\(object, object\)](#)  , [object.GetHashCode\(\)](#)  ,  
[object.GetType\(\)](#)  , [object.MemberwiseClone\(\)](#)  , [object.ReferenceEquals\(object, object\)](#)  ,  
[object.ToString\(\)](#) 

## Extension Methods

[TypeConversionExtensions.RonConvert\(object, Type\)](#) ,  
[TypeConversionExtensions.RonConvert<T>\(object\)](#)

# Constructors

## RonExponent(char?, char?, string?)

AST element for a float exponent.

```
public RonExponent(char? e, char? sign, string? digits)
```

## Parameters

e [char](#) ?

sign [char](#) ?

digits [string](#) 

# Fields

## digits

Digits

```
public string? digits
```

Field Value

[string](#)

## e

Exponent character if provided

```
public char? e
```

Field Value

[char](#)?

## sign

Sign.

```
public char? sign
```

Field Value

[char](#)?

# Methods

## Serialize()

Convert the element to a Ron string.

```
public string Serialize()
```

Returns

[string](#) 

## ValueString()

Get a value string representing the number in C#.

```
public string ValueString()
```

Returns

[string](#) 

# Class RonFloat

Namespace: [RonCS.AST](#)

Assembly: RonCS.dll

AST element representing a float value.

```
public class RonFloat : RonElement, INumberValue
```

## Inheritance

[object](#)  ← [RonElement](#)  ← RonFloat

## Implements

[INumberValue](#)

## Inherited Members

[object.Equals\(object\)](#) , [object.Equals\(object, object\)](#) , [object.GetHashCode\(\)](#) ,  
[object.GetType\(\)](#) , [object.MemberwiseClone\(\)](#) , [object.ReferenceEquals\(object, object\)](#) ,  
[object.ToString\(\)](#) 

## Extension Methods

[RonElementExtensions.IdentifierName\(RonElement?\)](#),  
[TypeConversionExtensions.RonConvert\(object, Type\)](#),  
[TypeConversionExtensions.RonConvert<T>\(object\)](#)

# Constructors

## RonFloat(char?, RonFloatNumber?, FloatSuffix?)

AST element representing a float value.

```
public RonFloat(char? sign = null, RonFloatNumber? num = null, FloatSuffix? suffix  
= null)
```

## Parameters

sign [char](#) .

num [RonFloatNumber](#)

suffix [FloatSuffix?](#)

## Fields

### num

The number value of the float.

```
public RonFloatNumber? num
```

### Field Value

[RonFloatNumber](#)

### sign

Sign of the float

```
public char? sign
```

### Field Value

[char](#)?

### suffix

The suffix of the float.

```
public FloatSuffix? suffix
```

### Field Value

[FloatSuffix?](#)

## Methods

## EvaluateNumber(Type?)

Evaluate the number into a C# type.

```
public object EvaluateNumber(Type? hint)
```

### Parameters

hint [Type](#)

### Returns

[object](#)

## RonPrint(RonPrintOptions)

Print the ron element as a Ron string.

```
public override string RonPrint(RonPrintOptions options)
```

### Parameters

options [RonPrintOptions](#)

### Returns

[string](#)

## ValueString()

String representing the value of the number. Used for C# type conversion.

```
public string ValueString()
```

### Returns

[string](#)



# Class RonFloatNumber

Namespace: [RonCS.AST](#)

Assembly: RonCS.dll

Base class for differentiating standard and special float numbers.

```
public abstract class RonFloatNumber
```

## Inheritance

[object](#)  ← RonFloatNumber

## Derived

[RonSpecialFloat](#), [RonStandardFloat](#)

## Inherited Members

[object.Equals\(object\)](#)  , [object.Equals\(object, object\)](#)  , [object.GetHashCode\(\)](#)  ,  
[object.GetType\(\)](#)  , [object.MemberwiseClone\(\)](#)  , [object.ReferenceEquals\(object, object\)](#)  ,  
[object.ToString\(\)](#) 

## Extension Methods

[TypeConversionExtensions.RonConvert\(object, Type\)](#) ,  
[TypeConversionExtensions.RonConvert<T>\(object\)](#)

# Methods

## Serialize()

Convert the element to a Ron string.

```
public abstract string Serialize()
```

## Returns

[string](#) 

## ValueString()

Get a string representing the value of the element.

```
public abstract string ValueString()
```

Returns

[string](#) 

# Class RonIdentifier

Namespace: [RonCS.AST](#)

Assembly: RonCS.dll

AST element for a ron identifier.

```
[Serializable]  
public class RonIdentifier : RonElement
```

## Inheritance

[object](#)  < [RonElement](#) < RonIdentifier

## Inherited Members

[object.Equals\(object\)](#)  , [object.Equals\(object, object\)](#)  , [object.GetHashCode\(\)](#)  ,  
[object.GetType\(\)](#)  , [object.MemberwiseClone\(\)](#)  , [object.ReferenceEquals\(object, object\)](#)  ,  
[object.ToString\(\)](#) 

## Extension Methods

[RonElementExtensions.IdentifierName\(RonElement?\)](#) ,  
[TypeConversionExtensions.RonConvert\(object, Type\)](#) ,  
[TypeConversionExtensions.RonConvert<T>\(object\)](#)

# Constructors

## RonIdentifier(string?)

AST element for a ron identifier.

```
public RonIdentifier(string? name = null)
```

## Parameters

name [string](#) 

# Fields

# Name

The name of the identifier.

```
public string? Name
```

## Field Value

[string](#) 

# Methods

## RonPrint(RonPrintOptions)

Print the ron element as a Ron string.

```
public override string RonPrint(RonPrintOptions options)
```

## Parameters

**options** [RonPrintOptions](#)

## Returns

[string](#) 

# Class RonInteger

Namespace: [RonCS.AST](#)

Assembly: RonCS.dll

AST element for an integer value.

```
public class RonInteger : RonElement, INumberValue
```

## Inheritance

[object](#)  ← [RonElement](#)  ← RonInteger

## Implements

[INumberValue](#)

## Inherited Members

[object.Equals\(object\)](#) , [object.Equals\(object, object\)](#) , [object.GetHashCode\(\)](#) ,  
[object.GetType\(\)](#) , [object.MemberwiseClone\(\)](#) , [object.ReferenceEquals\(object, object\)](#) ,  
[object.ToString\(\)](#) 

## Extension Methods

[RonElementExtensions.IdentifierName\(RonElement?\)](#),  
[TypeConversionExtensions.RonConvert\(object, Type\)](#),  
[TypeConversionExtensions.RonConvert<T>\(object\)](#)

# Constructors

## RonInteger(char?, RonUnsigned?, IntegerSuffix?)

AST element for an integer value.

```
public RonInteger(char? sign = null, RonUnsigned? digits = null, IntegerSuffix?  
integerSuffix = null)
```

## Parameters

sign [char](#) ?

digits [RonUnsigned](#)

`integerSuffix` [IntegerSuffix?](#)

## Fields

### digits

The digits for the number.

```
public RonUnsigned? digits
```

Field Value

[RonUnsigned](#)

### integerSuffix

The suffix for the number.

```
public IntegerSuffix? integerSuffix
```

Field Value

[IntegerSuffix?](#)

### sign

Integer sign, is provided.

```
public char? sign
```

Field Value

[char](#)?

## Methods

## EvaluateNumber(Type?)

Convert the value to a number.

```
public object EvaluateNumber(Type? hint)
```

### Parameters

hint [Type](#)

### Returns

[object](#)

## RonPrint(RonPrintOptions)

Print the ron element as a Ron string.

```
public override string RonPrint(RonPrintOptions options)
```

### Parameters

options [RonPrintOptions](#)

### Returns

[string](#)

## ValueString()

String representing the value of the number. Used for C# type conversion.

```
public string ValueString()
```

### Returns

[string](#)



# Class RonLexer

Namespace: [RonCS.AST](#)

Assembly: RonCS.dll

Base class for ron tokenizer

```
public class RonLexer
```

## Inheritance

[object](#)  ← RonLexer

## Inherited Members

[object.Equals\(object\)](#)  , [object.Equals\(object, object\)](#)  , [object.GetHashCode\(\)](#)  ,  
[object.GetType\(\)](#)  , [object.MemberwiseClone\(\)](#)  , [object.ReferenceEquals\(object, object\)](#)  ,  
[object.ToString\(\)](#) 

## Extension Methods

[TypeConversionExtensions.RonConvert\(object, Type\)](#) ,  
[TypeConversionExtensions.RonConvert<T>\(object\)](#)

# Methods

## Tokenize(string)

Tokenize the ron document and return the token list

```
public static TokenList<RonTokenKind> Tokenize(string source)
```

## Parameters

source [string](#) 

## Returns

TokenList<[RonTokenKind](#)>

# TryTokenize(string, out TokenList<RonTokenKind>, out Exception)

Try to tokenize the input.

```
public static bool TryTokenize(string source, out TokenList<RonTokenKind> tokens,
out Exception exception)
```

## Parameters

source [string](#)

The source code

tokens TokenList<[RonTokenKind](#)>

The token list if successful

exception [Exception](#)

The exception if failed

## Returns

[bool](#)

# Class RonList

Namespace: [RonCS.AST](#)

Assembly: RonCS.dll

AST element for a ron list.

```
public class RonList : RonElement
```

## Inheritance

[object](#)  ← [RonElement](#)  ← RonList

## Inherited Members

[object.Equals\(object\)](#) , [object.Equals\(object, object\)](#) , [object.GetHashCode\(\)](#) ,  
[object.GetType\(\)](#) , [object.MemberwiseClone\(\)](#) , [object.ReferenceEquals\(object, object\)](#) ,  
[object.ToString\(\)](#) 

## Extension Methods

[RonElementExtensions.IdentifierName\(RonElement?\)](#),  
[TypeConversionExtensions.RonConvert\(object, Type\)](#),  
[TypeConversionExtensions.RonConvert<T>\(object\)](#)

## Constructors

### RonList(params RonElement[]?)

AST element for a ron list.

```
public RonList(params RonElement[]? values)
```

## Parameters

values [RonElement](#)[]

## Fields

# Values

The values in the ron list.

```
public readonly RonElement[]? Values
```

## Field Value

[RonElement\[\]](#)

# Methods

## RonPrint(RonPrintOptions)

Print the ron element as a Ron string.

```
public override string RonPrint(RonPrintOptions options)
```

## Parameters

**options** [RonPrintOptions](#)

## Returns

[string](#) 

# Class RonMap

Namespace: [RonCS.AST](#)

Assembly: RonCS.dll

AST element for a Ron map

```
[Serializable]  
public class RonMap : RonElement
```

## Inheritance

[object](#)  ← [RonElement](#)  ← RonMap

## Inherited Members

[object.Equals\(object\)](#)  , [object.Equals\(object, object\)](#)  , [object.GetHashCode\(\)](#)  ,  
[object.GetType\(\)](#)  , [object.MemberwiseClone\(\)](#)  , [object.ReferenceEquals\(object, object\)](#)  ,  
[object.ToString\(\)](#) 

## Extension Methods

[RonElementExtensions.IdentifierName\(RonElement?\)](#) ,  
[TypeConversionExtensions.RonConvert\(object, Type\)](#) ,  
[TypeConversionExtensions.RonConvert<T>\(object\)](#)

# Constructors

## RonMap(params RonElement[]?)

AST element for a Ron map

```
public RonMap(params RonElement[]? values)
```

## Parameters

values [RonElement](#)[]

# Fields

# Values

Values in the ron map. If these are correct they should be map items.

```
public RonElement[]? Values
```

## Field Value

[RonElement\[\]](#)

# Methods

## RonPrint(RonPrintOptions)

Print the ron element as a Ron string.

```
public override string RonPrint(RonPrintOptions options)
```

## Parameters

**options** [RonPrintOptions](#)

## Returns

[string](#) 

# Class RonMapItem

Namespace: [RonCS.AST](#)

Assembly: RonCS.dll

AST element for an element in a ron map. In most cases key should be a ron string.

[Serializable]

```
public class RonMapItem : RonElement
```

## Inheritance

[object](#)  ← [RonElement](#)  ← RonMapItem

## Inherited Members

[object.Equals\(object\)](#)  , [object.Equals\(object, object\)](#)  , [object.GetHashCode\(\)](#)  ,  
[object.GetType\(\)](#)  , [object.MemberwiseClone\(\)](#)  , [object.ReferenceEquals\(object, object\)](#)  ,  
[object.ToString\(\)](#) 

## Extension Methods

[RonElementExtensions.IdentifierName\(RonElement?\)](#) ,  
[TypeConversionExtensions.RonConvert\(object, Type\)](#) ,  
[TypeConversionExtensions.RonConvert<T>\(object\)](#)

# Constructors

## RonMapItem(RonElement?, RonElement?)

AST element for an element in a ron map. In most cases key should be a ron string.

```
public RonMapItem(RonElement? key, RonElement? value)
```

## Parameters

key [RonElement](#)

value [RonElement](#)

# Fields

## Key

The key for the map item.

```
public RonElement? Key
```

## Field Value

[RonElement](#)

## Value

The value of the map item.

```
public RonElement? Value
```

## Field Value

[RonElement](#)

# Methods

## RonPrint(RonPrintOptions)

Print the ron element as a Ron string.

```
public override string RonPrint(RonPrintOptions options)
```

## Parameters

**options** [RonPrintOptions](#)

## Returns

[string](#) 



# Class RonMapStruct

Namespace: [RonCS.AST](#)

Assembly: RonCS.dll

AST element for a ron map struct.

[Serializable]

```
public class RonMapStruct : RonStruct
```

## Inheritance

[object](#)  ← [RonElement](#) ← [RonStruct](#) ← RonMapStruct

## Inherited Members

[RonStruct.Name](#) , [object.Equals\(object\)](#)  , [object.Equals\(object, object\)](#)  ,  
[object.GetHashCode\(\)](#)  , [object.GetType\(\)](#)  , [object.MemberwiseClone\(\)](#)  ,  
[object.ReferenceEquals\(object, object\)](#)  , [object.ToString\(\)](#) 

## Extension Methods

[RonElementExtensions.IdentifierName\(RonElement?\)](#) ,  
[TypeConversionExtensions.RonConvert\(object, Type\)](#) ,  
[TypeConversionExtensions.RonConvert<T>\(object\)](#)

# Constructors

## RonMapStruct(RonElement?, RonElement?)

AST element for a ron map struct.

```
public RonMapStruct(RonElement? name, RonElement? mapBody)
```

## Parameters

name [RonElement](#)

mapBody [RonElement](#)

# Properties

## MapBody

Body of the struct map.

```
public RonElement? MapBody { get; }
```

## Property Value

[RonElement](#)

# Methods

## RonPrint(RonPrintOptions)

Print the ron element as a Ron string.

```
public override string RonPrint(RonPrintOptions options)
```

## Parameters

**options** [RonPrintOptions](#)

## Returns

[string](#) 

# Class RonNamedValue

Namespace: [RonCS.AST](#)

Assembly: RonCS.dll

AST element for a ron named value. These are typically body elements for a ron struct.

```
[Serializable]  
public class RonNamedValue : RonElement
```

## Inheritance

[object](#)  ← [RonElement](#) ← RonNamedValue

## Inherited Members

[object.Equals\(object\)](#)  , [object.Equals\(object, object\)](#)  , [object.GetHashCode\(\)](#)  ,  
[object.GetType\(\)](#)  , [object.MemberwiseClone\(\)](#)  , [object.ReferenceEquals\(object, object\)](#)  ,  
[object.ToString\(\)](#) 

## Extension Methods

[RonElementExtensions.IdentifierName\(RonElement?\)](#) ,  
[TypeConversionExtensions.RonConvert\(object, Type\)](#) ,  
[TypeConversionExtensions.RonConvert<T>\(object\)](#)

# Constructors

## RonNamedValue(RonElement?, RonElement?)

AST element for a ron named value. These are typically body elements for a ron struct.

```
public RonNamedValue(RonElement? name = null, RonElement? value = null)
```

## Parameters

name [RonElement](#)

value [RonElement](#)

# Fields

## name

The name of the element. This should be a ron identifier.

```
public RonElement? name
```

## Field Value

[RonElement](#)

## value

The value of the element.

```
public RonElement? value
```

## Field Value

[RonElement](#)

# Methods

## RonPrint(RonPrintOptions)

Print the ron element as a Ron string.

```
public override string RonPrint(RonPrintOptions options)
```

## Parameters

**options** [RonPrintOptions](#)

## Returns

[string](#) 



# Class RonNamedValueStruct

Namespace: [RonCS.AST](#)

Assembly: RonCS.dll

AST element for a ron struct with named values.

```
[Serializable]  
public class RonNamedValueStruct : RonStruct
```

## Inheritance

[object](#)  ← [RonElement](#) ← [RonStruct](#) ← RonNamedValueStruct

## Inherited Members

[RonStruct.Name](#) , [object.Equals\(object\)](#)  , [object.Equals\(object, object\)](#)  ,  
[object.GetHashCode\(\)](#)  , [object.GetType\(\)](#)  , [object.MemberwiseClone\(\)](#)  ,  
[object.ReferenceEquals\(object, object\)](#)  , [object.ToString\(\)](#) 

## Extension Methods

[RonElementExtensions.IdentifierName\(RonElement?\)](#) ,  
[TypeConversionExtensions.RonConvert\(object, Type\)](#) ,  
[TypeConversionExtensions.RonConvert<T>\(object\)](#)

## Constructors

RonNamedValueStruct(RonElement?, params  
RonElement[]?)

AST element for a ron struct with named values.

```
public RonNamedValueStruct(RonElement? name, params RonElement[]? body)
```

## Parameters

name [RonElement](#)

body [RonElement\[\]](#)

# Fields

## Body

The body of the named value struct. These should be RonNamedValues.

```
public RonElement[]? Body
```

## Field Value

[RonElement\[\]](#)

# Methods

## RonPrint(RonPrintOptions)

Print the ron element as a Ron string.

```
public override string RonPrint(RonPrintOptions options)
```

## Parameters

**options** [RonPrintOptions](#)

## Returns

[string](#) 

# Class RonNone

Namespace: [RonCS.AST](#)

Assembly: RonCS.dll

AST element representing a ron none.

```
[Serializable]  
public class RonNone : RonElement
```

## Inheritance

[object](#)  ← [RonElement](#)  ← RonNone

## Inherited Members

[object.Equals\(object\)](#)  , [object.Equals\(object, object\)](#)  , [object.GetHashCode\(\)](#)  ,  
[object.GetType\(\)](#)  , [object.MemberwiseClone\(\)](#)  , [object.ReferenceEquals\(object, object\)](#)  ,  
[object.ToString\(\)](#) 

## Extension Methods

[RonElementExtensions.IdentifierName\(RonElement?\)](#) ,  
[TypeConversionExtensions.RonConvert\(object, Type\)](#) ,  
[TypeConversionExtensions.RonConvert<T>\(object\)](#)

# Methods

## RonPrint(RonPrintOptions)

Print the ron element as a Ron string.

```
public override string RonPrint(RonPrintOptions options)
```

## Parameters

**options** [RonPrintOptions](#)

## Returns

[string](#) 

# Class RonParser

Namespace: [RonCS.AST](#)

Assembly: RonCS.dll

Parser for ron documents

```
public static class RonParser
```

## Inheritance

[object](#)  ← RonParser

## Inherited Members

[object.Equals\(object\)](#)  , [object.Equals\(object, object\)](#)  , [object.GetHashCode\(\)](#)  ,  
[object.GetType\(\)](#)  , [object.MemberwiseClone\(\)](#)  , [object.ReferenceEquals\(object, object\)](#)  ,  
[object.ToString\(\)](#) 

## Fields

### Boolean

Boolean = 'true' | 'false';

```
public static TokenListParser<RonTokenKind, RonElement> Boolean
```

### Field Value

TokenListParser<[RonTokenKind](#), [RonElement](#)>

### Char

Character parser

```
public static TokenListParser<RonTokenKind, RonElement> Char
```

### Field Value

TokenListParser<[RonTokenKind](#), [RonElement](#)>

## Identifier

Identifier = identifier | rawIdentifier;

```
public static TokenListParser<RonTokenKind, RonElement> Identifier
```

## Field Value

TokenListParser<[RonTokenKind](#), [RonElement](#)>

## List

RonList

```
public static TokenListParser<RonTokenKind, RonElement> List
```

## Field Value

TokenListParser<[RonTokenKind](#), [RonElement](#)>

## Map

RonMap

```
public static TokenListParser<RonTokenKind, RonElement> Map
```

## Field Value

TokenListParser<[RonTokenKind](#), [RonElement](#)>

## MapItem

MapItem = Value ':' Value;

```
public static TokenListParser<RonTokenKind, RonElement> MapItem
```

Field Value

```
TokenListParser<RonTokenKind, RonElement>
```

## MapItemSet

```
MapItemSet = { MapItem } [''];
```

```
public static TokenListParser<RonTokenKind, IEnumerable<RonElement>> MapItemSet
```

Field Value

```
TokenListParser<RonTokenKind, IEnumerable<RonElement>>
```

## MapStruct

```
Summary MapStruct = Identifier Map
```

```
public static TokenListParser<RonTokenKind, RonElement> MapStruct
```

Field Value

```
TokenListParser<RonTokenKind, RonElement>
```

## NameFieldStruct

```
NamedFieldStruct = Identifier '(' [NamedValueSet] ')';
```

```
public static TokenListParser<RonTokenKind, RonElement> NameFieldStruct
```

Field Value

```
TokenListParser<RonTokenKind, RonElement>
```

# NamedValue

NamedValue = Identifier ':' Value

```
public static TokenListParser<RonTokenKind, RonElement> NamedValue
```

## Field Value

TokenListParser<[RonTokenKind](#), [RonElement](#)>

# NamedValueSet

NamedValueSet = NamedValue { ',' NamedValue } [',']

```
public static TokenListParser<RonTokenKind, IEnumerable<RonElement>> NamedValueSet
```

## Field Value

TokenListParser<[RonTokenKind](#), [IEnumerable](#)  <[RonElement](#)>>

# None

None = 'None';

```
public static TokenListParser<RonTokenKind, RonElement> None
```

## Field Value

TokenListParser<[RonTokenKind](#), [RonElement](#)>

# Number

Number = Integer;

```
public static TokenListParser<RonTokenKind, RonElement> Number
```

## Field Value

TokenListParser<[RonTokenKind](#), [RonElement](#)>

## Option

Option = Some | None;

```
public static TokenListParser<RonTokenKind, RonElement> Option
```

## Field Value

TokenListParser<[RonTokenKind](#), [RonElement](#)>

## Primitive

Primitive = Boolean;

```
public static TokenListParser<RonTokenKind, RonElement> Primitive
```

## Field Value

TokenListParser<[RonTokenKind](#), [RonElement](#)>

## Range

Range = RangeBinary | RangeFrom | RangeTo | RangeFull;

```
public static TokenListParser<RonTokenKind, RonElement> Range
```

## Field Value

TokenListParser<[RonTokenKind](#), [RonElement](#)>

## RangeBinary

RangeBinary = Number RangeOperator Number;

```
public static TokenListParser<RonTokenKind, RonElement> RangeBinary
```

Field Value

TokenListParser<[RonTokenKind](#), [RonElement](#)>

## RangeFrom

RangeFrom = Number '..';

```
public static TokenListParser<RonTokenKind, RonElement> RangeFrom
```

Field Value

TokenListParser<[RonTokenKind](#), [RonElement](#)>

## RangeFull

RangeFull = '..';

```
public static TokenListParser<RonTokenKind, RonElement> RangeFull
```

Field Value

TokenListParser<[RonTokenKind](#), [RonElement](#)>

## RangeOperator

RangeOperator = '..' | '..=';

```
public static TokenListParser<RonTokenKind, RonRangeOperator> RangeOperator
```

Field Value

TokenListParser<[RonTokenKind](#), [RonRangeOperator](#)>

## RangeOperatorExclusive

Ron range operator

```
public static TokenListParser<RonTokenKind, RonRangeOperator> RangeOperatorExclusive
```

Field Value

TokenListParser<[RonTokenKind](#), [RonRangeOperator](#)>

## RangeTo

RangeTo = RangeOperator Number;

```
public static TokenListParser<RonTokenKind, RonElement> RangeTo
```

Field Value

TokenListParser<[RonTokenKind](#), [RonElement](#)>

## Ron

Ron = Extensions Value;

```
public static TokenListParser<RonTokenKind, RonElement> Ron
```

Field Value

TokenListParser<[RonTokenKind](#), [RonElement](#)>

## Some

Some = 'Some' '(' Value ')';

```
public static TokenListParser<RonTokenKind, RonElement> Some
```

Field Value

```
TokenListParser<RonTokenKind, RonElement>
```

## String

String parser

```
public static TokenListParser<RonTokenKind, RonElement> String
```

Field Value

```
TokenListParser<RonTokenKind, RonElement>
```

## Struct

Struct = TupleStruct | NamedFieldStruct | UnitStruct;

```
public static TokenListParser<RonTokenKind, RonElement> Struct
```

Field Value

```
TokenListParser<RonTokenKind, RonElement>
```

## Tuple

Tuple = '(' [ValueSet] ')';

```
public static TokenListParser<RonTokenKind, RonElement> Tuple
```

Field Value

```
TokenListParser<RonTokenKind, RonElement>
```

# TupleStruct

TupleStruct = Identifier Tuple;

```
public static TokenListParser<RonTokenKind, RonElement> TupleStruct
```

## Field Value

TokenListParser<[RonTokenKind](#), [RonElement](#)>

# UnitStruct

UnitStruct = Identifier;

```
public static TokenListParser<RonTokenKind, RonElement> UnitStruct
```

## Field Value

TokenListParser<[RonTokenKind](#), [RonElement](#)>

# Value

Value = Option | Tuple | Struct | Map | Primitive

```
public static TokenListParser<RonTokenKind, RonElement> Value
```

## Field Value

TokenListParser<[RonTokenKind](#), [RonElement](#)>

# ValueSet

ValueSet = Value { Value ',' } [,']

```
public static TokenListParser<RonTokenKind, IEnumerable<RonElement>> ValueSet
```

## Field Value

TokenListParser<[RonTokenKind](#), [IEnumerable](#) <[RonElement](#)>>

# Class RonRange

Namespace: [RonCS.AST](#)

Assembly: RonCS.dll

AST element for a Ron range.

```
public class RonRange : RonElement
```

## Inheritance

[object](#)  ← [RonElement](#)  ← RonRange

## Inherited Members

[object.Equals\(object\)](#) , [object.Equals\(object, object\)](#) , [object.GetHashCode\(\)](#) ,  
[object.GetType\(\)](#) , [object.MemberwiseClone\(\)](#) , [object.ReferenceEquals\(object, object\)](#) ,  
[object.ToString\(\)](#) 

## Extension Methods

[RonElementExtensions.IdentifierName\(RonElement?\)](#),  
[TypeConversionExtensions.RonConvert\(object, Type\)](#),  
[TypeConversionExtensions.RonConvert<T>\(object\)](#)

# Constructors

## RonRange(RonElement?, RonRangeOperator?, RonElement?)

AST element for a Ron range.

```
public RonRange(RonElement? lower = null, RonRangeOperator? op = null, RonElement?  
upper = null)
```

## Parameters

**lower** [RonElement](#)

**op** [RonRangeOperator?](#)

**upper** [RonElement](#)

# Fields

## lower

The lower value of the range.

```
public RonElement? lower
```

## Field Value

[RonElement](#)

## op

The operator of the range.

```
public RonRangeOperator? op
```

## Field Value

[RonRangeOperator?](#)

## upper

The upper value of the range.

```
public RonElement? upper
```

## Field Value

[RonElement](#)

# Methods

## RonPrint(RonPrintOptions)

Print the ron element as a Ron string.

```
public override string RonPrint(RonPrintOptions options)
```

## Parameters

`options` [RonPrintOptions](#)

## Returns

[string](#) 

# Enum RonRangeOperator

Namespace: [RonCS.AST](#)

Assembly: RonCS.dll

The ron element operator.

```
public enum RonRangeOperator
```

## Extension Methods

[TypeConversionExtensions.RonConvert\(object, Type\)](#) ,  
[TypeConversionExtensions.RonConvert<T>\(object\)](#)

## Fields

**Exclusive = 0**

Exclude the upper bound.

**Inclusive = 1**

Include the upper bound.

# Class RonRawIdentifier

Namespace: [RonCS.AST](#)

Assembly: RonCS.dll

AST element for a raw identifier.

```
[Serializable]  
public class RonRawIdentifier : RonElement
```

## Inheritance

[object](#)  ← [RonElement](#)  ← RonRawIdentifier

## Inherited Members

[object.Equals\(object\)](#)  , [object.Equals\(object, object\)](#)  , [object.GetHashCode\(\)](#)  ,  
[object.GetType\(\)](#)  , [object.MemberwiseClone\(\)](#)  , [object.ReferenceEquals\(object, object\)](#)  ,  
[object.ToString\(\)](#) 

## Extension Methods

[RonElementExtensions.IdentifierName\(RonElement?\)](#) ,  
[TypeConversionExtensions.RonConvert\(object, Type\)](#) ,  
[TypeConversionExtensions.RonConvert<T>\(object\)](#)

# Constructors

## RonRawIdentifier(string?)

AST element for a raw identifier.

```
public RonRawIdentifier(string? name = null)
```

## Parameters

name [string](#) 

# Fields

# Name

The name of the identifier.

```
public string? Name
```

## Field Value

[string](#) 

# Methods

## IdentifierName()

The string name of the identifier.

```
public string IdentifierName()
```

## Returns

[string](#) 

## RonPrint(RonPrintOptions)

Print the ron element as a Ron string.

```
public override string RonPrint(RonPrintOptions options)
```

## Parameters

**options** [RonPrintOptions](#)

## Returns

[string](#) 

# Class RonSome

Namespace: [RonCS.AST](#)

Assembly: RonCS.dll

AST element for a ron some.

```
[Serializable]  
public class RonSome : RonElement
```

## Inheritance

[object](#)  ← [RonElement](#)  ← RonSome

## Inherited Members

[object.Equals\(object\)](#) , [object.Equals\(object, object\)](#) , [object.GetHashCode\(\)](#) ,  
[object.GetType\(\)](#) , [object.MemberwiseClone\(\)](#) , [object.ReferenceEquals\(object, object\)](#) ,  
[object.ToString\(\)](#) 

## Extension Methods

[RonElementExtensions.IdentifierName\(RonElement?\)](#) ,  
[TypeConversionExtensions.RonConvert\(object, Type\)](#) ,  
[TypeConversionExtensions.RonConvert<T>\(object\)](#)

# Constructors

## RonSome(RonElement?)

AST element for a ron some.

```
public RonSome(RonElement? value = null)
```

## Parameters

value [RonElement](#)

# Fields

# value

The value inside the some.

```
public RonElement? value
```

## Field Value

[RonElement](#)

# Methods

## RonPrint(RonPrintOptions)

Print the ron element as a Ron string.

```
public override string RonPrint(RonPrintOptions options)
```

## Parameters

**options** [RonPrintOptions](#)

## Returns

[string](#) 

# Class RonSpecialFloat

Namespace: [RonCS.AST](#)

Assembly: RonCS.dll

AST element for a special float number.

```
public class RonSpecialFloat : RonFloatNumber
```

## Inheritance

[object](#)  ← [RonFloatNumber](#) ← RonSpecialFloat

## Inherited Members

[object.Equals\(object\)](#)  , [object.Equals\(object, object\)](#)  , [object.GetHashCode\(\)](#)  ,  
[object.GetType\(\)](#)  , [object.MemberwiseClone\(\)](#)  , [object.ReferenceEquals\(object, object\)](#)  ,  
[object.ToString\(\)](#) 

## Extension Methods

[TypeConversionExtensions.RonConvert\(object, Type\)](#) ,  
[TypeConversionExtensions.RonConvert<T>\(object\)](#)

## Constructors

### RonSpecialFloat(SpecialFloatType?)

AST element for a special float number.

```
public RonSpecialFloat(SpecialFloatType? type)
```

## Parameters

type [SpecialFloatType?](#)

## Fields

type

The type of the float.

```
public SpecialFloatType? type
```

Field Value

[SpecialFloatType?](#)

## Methods

### Serialize()

Convert the element to a Ron string.

```
public override string Serialize()
```

Returns

[string](#)

### ValueString()

Get a string representing the value of the element.

```
public override string ValueString()
```

Returns

[string](#)

# Class RonStandardFloat

Namespace: [RonCS.AST](#)

Assembly: RonCS.dll

AST element representing a standard float number.

```
public class RonStandardFloat : RonFloatNumber
```

## Inheritance

[object](#)  ← [RonFloatNumber](#) ← RonStandardFloat

## Inherited Members

[object.Equals\(object\)](#)  , [object.Equals\(object, object\)](#)  , [object.GetHashCode\(\)](#)  ,  
[object.GetType\(\)](#)  , [object.MemberwiseClone\(\)](#)  , [object.ReferenceEquals\(object, object\)](#)  ,  
[object.ToString\(\)](#) 

## Extension Methods

[TypeConversionExtensions.RonConvert\(object, Type\)](#) ,  
[TypeConversionExtensions.RonConvert<T>\(object\)](#)

## Constructors

### RonStandardFloat(string?, RonExponent?)

AST element representing a standard float number.

```
public RonStandardFloat(string? digits, RonExponent? exponent)
```

## Parameters

**digits** [string](#) 

**exponent** [RonExponent](#)

## Fields

## digits

The digits of the float, if provided.

```
public string? digits
```

Field Value

[string](#)↗

## exponent

The exponent of the float, if provided.

```
public RonExponent? exponent
```

Field Value

[RonExponent](#)

## Methods

### Serialize()

Convert the element to a Ron string.

```
public override string Serialize()
```

Returns

[string](#)↗

### ValueString()

Get a string representing the value of the element.

```
public override string ValueString()
```

Returns

[string](#) 

# Class RonString

Namespace: [RonCS.AST](#)

Assembly: RonCS.dll

AST element representing a string.

```
public class RonString : RonElement
```

## Inheritance

[object](#)  ← [RonElement](#)  ← RonString

## Inherited Members

[object.Equals\(object\)](#) , [object.Equals\(object, object\)](#) , [object.GetHashCode\(\)](#) ,  
[object.GetType\(\)](#) , [object.MemberwiseClone\(\)](#) , [object.ReferenceEquals\(object, object\)](#) ,  
[object.ToString\(\)](#) 

## Extension Methods

[RonElementExtensions.IdentifierName\(RonElement?\)](#),  
[TypeConversionExtensions.RonConvert\(object, Type\)](#),  
[TypeConversionExtensions.RonConvert<T>\(object\)](#)

## Constructors

### RonString(params StringContent[])

AST element representing a string.

```
public RonString(params StringContent[] content)
```

## Parameters

**content** [StringContent](#)[]

## Fields

# content

The content of the RON string.

```
public StringContent[] content
```

Field Value

[StringContent\[\]](#)

## Methods

### Evaluate()

Evaluate this AST element as a C# string.

```
public string Evaluate()
```

Returns

[string](#)

### RonPrint(RonPrintOptions)

Print the ron element as a Ron string.

```
public override string RonPrint(RonPrintOptions options)
```

Parameters

**options** [RonPrintOptions](#)

Returns

[string](#)

# Class RonStringLit

Namespace: [RonCS.AST](#)

Assembly: RonCS.dll

Literal string content.

```
public class RonStringLit : StringContent
```

## Inheritance

[object](#)  ← RonStringLit

## Implements

[StringContent](#)

## Inherited Members

[object.Equals\(object\)](#)  , [object.Equals\(object, object\)](#)  , [object.GetHashCode\(\)](#)  ,  
[object.GetType\(\)](#)  , [object.MemberwiseClone\(\)](#)  , [object.ReferenceEquals\(object, object\)](#)  ,  
[object.ToString\(\)](#) 

## Extension Methods

[TypeConversionExtensions.RonConvert\(object, Type\)](#) ,  
[TypeConversionExtensions.RonConvert<T>\(object\)](#)

# Constructors

## RonStringLit(string)

Literal string content.

```
public RonStringLit(string value)
```

## Parameters

value [string](#) 

# Fields

# value

The value of the string literal.

```
public string value
```

## Field Value

[string](#) 

## Methods

### EvaluateString()

Evaluate the element as a C# string.

```
public string EvaluateString()
```

## Returns

[string](#) 

### Serialize()

Convert the element to a RON string.

```
public string Serialize()
```

## Returns

[string](#) 

# Class RonStringRawContent

Namespace: [RonCS.AST](#)

Assembly: RonCS.dll

Raw string.

```
public class RonStringRawContent : StringContent
```

## Inheritance

[object](#)  ← RonStringRawContent

## Implements

[StringContent](#)

## Inherited Members

[object.Equals\(object\)](#)  , [object.Equals\(object, object\)](#)  , [object.GetHashCode\(\)](#)  ,  
[object.GetType\(\)](#)  , [object.MemberwiseClone\(\)](#)  , [object.ReferenceEquals\(object, object\)](#)  ,  
[object.ToString\(\)](#) 

## Extension Methods

[TypeConversionExtensions.RonConvert\(object, Type\)](#) ,  
[TypeConversionExtensions.RonConvert<T>\(object\)](#)

# Constructors

## RonStringRawContent(StringContent)

Raw string.

```
public RonStringRawContent(StringContent content)
```

## Parameters

**content** [StringContent](#)

# Fields

# content

The content of this raw string.

```
public StringContent content
```

Field Value

[StringContent](#)

## Methods

### EvaluateString()

Evaluate the element as a C# string.

```
public string EvaluateString()
```

Returns

[string](#)

### Serialize()

Convert the element to a RON string.

```
public string Serialize()
```

Returns

[string](#)

# Class RonStringRawLit

Namespace: [RonCS.AST](#)

Assembly: RonCS.dll

Raw string literal.

```
public class RonStringRawLit : StringContent
```

## Inheritance

[object](#)  ← RonStringRawLit

## Implements

[StringContent](#)

## Inherited Members

[object.Equals\(object\)](#)  , [object.Equals\(object, object\)](#)  , [object.GetHashCode\(\)](#)  ,  
[object.GetType\(\)](#)  , [object.MemberwiseClone\(\)](#)  , [object.ReferenceEquals\(object, object\)](#)  ,  
[object.ToString\(\)](#) 

## Extension Methods

[TypeConversionExtensions.RonConvert\(object, Type\)](#) ,  
[TypeConversionExtensions.RonConvert<T>\(object\)](#)

# Constructors

## RonStringRawLit(string)

Raw string literal.

```
public RonStringRawLit(string source)
```

## Parameters

source [string](#) 

# Fields

## source

The string source code.

```
public string source
```

## Field Value

[string](#) 

## Methods

### EvaluateString()

Evaluate the element as a C# string.

```
public string EvaluateString()
```

## Returns

[string](#) 

### Serialize()

Convert the element to a RON string.

```
public string Serialize()
```

## Returns

[string](#) 

# Class RonStruct

Namespace: [RonCS.AST](#)

Assembly: RonCS.dll

Base class for struct AST elements.

```
[Serializable]  
public abstract class RonStruct : RonElement
```

## Inheritance

[object](#)  ← [RonElement](#) ← RonStruct

## Derived

[RonMapStruct](#), [RonNamedValueStruct](#), [RonTupleStruct](#), [RonUnitStruct](#)

## Inherited Members

[RonElement.RonPrint\(RonPrintOptions\)](#), [object.Equals\(object\)](#) , [object.Equals\(object, object\)](#) ,  
[object.GetHashCode\(\)](#) , [object.GetType\(\)](#) , [object.MemberwiseClone\(\)](#) ,  
[object.ReferenceEquals\(object, object\)](#) , [object.ToString\(\)](#) 

## Extension Methods

[RonElementExtensions.IdentifierName\(RonElement?\)](#),  
[TypeConversionExtensions.RonConvert\(object, Type\)](#),  
[TypeConversionExtensions.RonConvert<T>\(object\)](#)

# Constructors

## RonStruct(RonElement?)

Base class for struct AST elements.

```
protected RonStruct(RonElement? name)
```

## Parameters

name [RonElement](#)

# Properties

## Name

The name of the struct, or null if it is not provided.

```
public RonElement? Name { get; set; }
```

## Property Value

[RonElement](#)

# Enum RonTokenKind

Namespace: [RonCS.AST](#)

Assembly: RonCS.dll

Tokens for the RON language.

```
public enum RonTokenKind
```

## Extension Methods

[TypeConversionExtensions.RonConvert\(object, Type\)](#) ,  
[TypeConversionExtensions.RonConvert<T>\(object\)](#)

## Fields

Char = 13

Any XID character.

ClosedCurly = 10

}

ClosedParen = 6

)

ClosedSquare = 8

]

Colon = 1

;

Comma = 0

,

False = 15

false

Hash = 2

Identifier = 18

XID identifier

None = 12

None

Number = 16

Any ron number

OpenCurly = 9

{

OpenParen = 5

(

OpenSquare = 7

[

RangeExclusive = 3

..

RangeInclusive = 4

..=

RawIdentifier = 19

Raw identifier

Some = 11

Some

String = 17

Any ron string

True = 14

true

# Class RonTuple

Namespace: [RonCS.AST](#)

Assembly: RonCS.dll

AST element for a Ron tuple.

```
[Serializable]  
public class RonTuple : RonElement
```

## Inheritance

[object](#)  ← [RonElement](#) ← RonTuple

## Inherited Members

[object.Equals\(object\)](#)  , [object.Equals\(object, object\)](#)  , [object.GetHashCode\(\)](#)  ,  
[object.GetType\(\)](#)  , [object.MemberwiseClone\(\)](#)  , [object.ReferenceEquals\(object, object\)](#)  ,  
[object.ToString\(\)](#) 

## Extension Methods

[RonElementExtensions.IdentifierName\(RonElement?\)](#) ,  
[TypeConversionExtensions.RonConvert\(object, Type\)](#) ,  
[TypeConversionExtensions.RonConvert<T>\(object\)](#)

# Constructors

## RonTuple(params RonElement[]?)

AST element for a Ron tuple.

```
public RonTuple(params RonElement[]? values)
```

## Parameters

values [RonElement](#)[]

# Fields

# Values

Tuple values.

```
public RonElement[]? Values
```

Field Value

[RonElement\[\]](#)

# Methods

## RonPrint(RonPrintOptions)

Print the ron element as a Ron string.

```
public override string RonPrint(RonPrintOptions options)
```

Parameters

**options** [RonPrintOptions](#)

Returns

[string](#) 

# Class RonTupleStruct

Namespace: [RonCS.AST](#)

Assembly: RonCS.dll

AST element for a struct with a tuple body.

```
[Serializable]  
public class RonTupleStruct : RonStruct
```

## Inheritance

[object](#)  ← [RonElement](#) ← [RonStruct](#) ← RonTupleStruct

## Inherited Members

[RonStruct.Name](#) , [object.Equals\(object\)](#)  , [object.Equals\(object, object\)](#)  ,  
[object.GetHashCode\(\)](#)  , [object.GetType\(\)](#)  , [object.MemberwiseClone\(\)](#)  ,  
[object.ReferenceEquals\(object, object\)](#)  , [object.ToString\(\)](#) 

## Extension Methods

[RonElementExtensions.IdentifierName\(RonElement?\)](#) ,  
[TypeConversionExtensions.RonConvert\(object, Type\)](#) ,  
[TypeConversionExtensions.RonConvert<T>\(object\)](#)

# Constructors

## RonTupleStruct(RonElement?, RonElement?)

AST element for a struct with a tuple body.

```
public RonTupleStruct(RonElement? name, RonElement? body)
```

## Parameters

name [RonElement](#)

body [RonElement](#)

# Fields

## Body

The body of the tuple. This should be a `RonTuple`.

```
public RonElement? Body
```

## Field Value

[RonElement](#)

# Methods

## RonPrint(RonPrintOptions)

Print the ron element as a Ron string.

```
public override string RonPrint(RonPrintOptions options)
```

## Parameters

`options` [RonPrintOptions](#)

## Returns

[string](#) 

# Class RonUnicodeEscape

Namespace: [RonCS.AST](#)

Assembly: RonCS.dll

Unicode escape content.

```
public class RonUnicodeEscape : StringContent
```

## Inheritance

[object](#)  ← RonUnicodeEscape

## Implements

[StringContent](#)

## Inherited Members

[object.Equals\(object\)](#)  , [object.Equals\(object, object\)](#)  , [object.GetHashCode\(\)](#)  ,  
[object.GetType\(\)](#)  , [object.MemberwiseClone\(\)](#)  , [object.ReferenceEquals\(object, object\)](#)  ,  
[object.ToString\(\)](#) 

## Extension Methods

[TypeConversionExtensions.RonConvert\(object, Type\)](#) ,  
[TypeConversionExtensions.RonConvert<T>\(object\)](#)

# Constructors

## RonUnicodeEscape(string)

Unicode escape content.

```
public RonUnicodeEscape(string source)
```

## Parameters

source [string](#) 

# Fields

## source

RON source code.

```
public string source
```

## Field Value

[string](#) 

## Methods

### EvaluateString()

Evaluate the element as a C# string.

```
public string EvaluateString()
```

## Returns

[string](#) 

### Serialize()

Convert the element to a RON string.

```
public string Serialize()
```

## Returns

[string](#) 

# Class RonUnitStruct

Namespace: [RonCS.AST](#)

Assembly: RonCS.dll

AST element for a ron Unit struct with no body.

```
[Serializable]  
public class RonUnitStruct : RonStruct
```

## Inheritance

[object](#)  < [RonElement](#) < [RonStruct](#) < RonUnitStruct

## Inherited Members

[RonStruct.Name](#) , [object.Equals\(object\)](#)  , [object.Equals\(object, object\)](#)  ,  
[object.GetHashCode\(\)](#)  , [object.GetType\(\)](#)  , [object.MemberwiseClone\(\)](#)  ,  
[object.ReferenceEquals\(object, object\)](#)  , [object.ToString\(\)](#) 

## Extension Methods

[RonElementExtensions.IdentifierName\(RonElement?\)](#) ,  
[TypeConversionExtensions.RonConvert\(object, Type\)](#) ,  
[TypeConversionExtensions.RonConvert<T>\(object\)](#)

# Constructors

## RonUnitStruct(RonElement?)

AST element for a ron Unit struct with no body.

```
public RonUnitStruct(RonElement? name)
```

## Parameters

name [RonElement](#)

# Methods

# RonPrint(RonPrintOptions)

Print the ron element as a Ron string.

```
public override string RonPrint(RonPrintOptions options)
```

## Parameters

`options` [RonPrintOptions](#)

## Returns

[string](#) 

# Class RonUnsigned

Namespace: [RonCS.AST](#)

Assembly: RonCS.dll

Unsigned integer value.

```
public class RonUnsigned : INumberValue
```

## Inheritance

[object](#)  ← RonUnsigned

## Implements

[INumberValue](#)

## Inherited Members

[object.Equals\(object\)](#)  , [object.Equals\(object, object\)](#)  , [object.GetHashCode\(\)](#)  ,  
[object.GetType\(\)](#)  , [object.MemberwiseClone\(\)](#)  , [object.ReferenceEquals\(object, object\)](#)  ,  
[object.ToString\(\)](#) 

## Extension Methods

[TypeConversionExtensions.RonConvert\(object, Type\)](#) ,  
[TypeConversionExtensions.RonConvert<T>\(object\)](#)

# Constructors

## RonUnsigned(UnsignedPrefix?, string?)

Unsigned integer value.

```
public RonUnsigned(UnsignedPrefix? prefix = null, string? digits = null)
```

## Parameters

**prefix** [UnsignedPrefix?](#)

**digits** [string](#) 

# Fields

## digits

The digits for the unsigned value.

```
public string? digits
```

## Field Value

[string](#)↗

## prefix

Unsigned prefix value.

```
public UnsignedPrefix? prefix
```

## Field Value

[UnsignedPrefix?](#)

# Methods

## EvaluateNumber(Type?)

Convert the value to a number.

```
public object EvaluateNumber(Type? hint)
```

## Parameters

hint [Type](#)↗

## Returns

[object](#)↗

## Serialize()

Convert the number to a Ron string.

```
public string Serialize()
```

Returns

[string](#) 

## ValueString()

String representing the value of the number. Used for C# type conversion.

```
public string ValueString()
```

Returns

[string](#) 

# Enum SpecialFloatType

Namespace: [RonCS.AST](#)

Assembly: RonCS.dll

Type of a special float.

```
public enum SpecialFloatType
```

## Extension Methods

[TypeConversionExtensions.RonConvert\(object, Type\)](#) ,  
[TypeConversionExtensions.RonConvert<T>\(object\)](#)

## Fields

`NaN = 1`

Not a number

`inf = 0`

Infinity

# Interface StringContent

Namespace: [RonCS.AST](#)

Assembly: RonCS.dll

Represents part of a string.

```
public interface StringContent
```

## Extension Methods

[TypeConversionExtensions.RonConvert\(object, Type\)](#) ,  
[TypeConversionExtensions.RonConvert<T>\(object\)](#)

## Methods

### EvaluateString()

Evaluate the element as a C# string.

```
string EvaluateString()
```

Returns

[string](#) 

### Serialize()

Convert the element to a RON string.

```
string Serialize()
```

Returns

[string](#) 

# Class StringParser

Namespace: [RonCS.AST](#)

Assembly: RonCS.dll

Parser for Ron strings.

```
public static class StringParser
```

## Inheritance

[object](#)  ← StringParser

## Inherited Members

[object.Equals\(object\)](#)  , [object.Equals\(object, object\)](#)  , [object.GetHashCode\(\)](#)  ,  
[object.GetType\(\)](#)  , [object.MemberwiseClone\(\)](#)  , [object.ReferenceEquals\(object, object\)](#)  ,  
[object.ToString\(\)](#) 

## Fields

### Char\_Parser

Character or escaped character

```
public static TextParser<RonElement> Char_Parser
```

### Field Value

TextParser<[RonElement](#)>

### DigitBinary\_Parser

DigitBinary

```
public static TextParser<char> DigitBinary_Parser
```

### Field Value

TextParser<[char](#)>

## DigitHexDecimal\_Parser

DigitHexDecimal

```
public static TextParser<char> DigitHexDecimal_Parser
```

Field Value

TextParser<[char](#)>

## DigitOctal\_Parser

DigitOctal

```
public static TextParser<char> DigitOctal_Parser
```

Field Value

TextParser<[char](#)>

## Digit\_Parser

Digit

```
public static TextParser<char> Digit_Parser
```

Field Value

TextParser<[char](#)>

## EscapeAscii\_Parser

Ascii character

```
public static TextParser<StringContent> EscapeAscii_Parser
```

Field Value

TextParser<[StringContent](#)>

## EscapeByte\_Parser

Byte

```
public static TextParser<StringContent> EscapeByte_Parser
```

Field Value

TextParser<[StringContent](#)>

## EscapeUnicode\_Parser

Escaped Unicode

```
public static TextParser<StringContent> EscapeUnicode_Parser
```

Field Value

TextParser<[StringContent](#)>

## StringEscapeContent\_Parser

Any escaped string element

```
public static TextParser<StringContent> StringEscapeContent_Parser
```

Field Value

TextParser<[StringContent](#)>

# StringEscape\_Parser

Escaped string

```
public static TextParser<StringContent> StringEscape_Parser
```

Field Value

TextParser<[StringContent](#)>

# StringRawContent\_Parser

Raw content parser

```
public static TextParser<StringContent> StringRawContent_Parser
```

Field Value

TextParser<[StringContent](#)>

# StringRaw\_Parser

Raw string parser

```
public static TextParser<RonString> StringRaw_Parser
```

Field Value

TextParser<[RonString](#)>

# StringSTD\_Parser

Standard string

```
public static TextParser<RonString> StringSTD_Parser
```

Field Value

TextParser<[RonString](#)>

## String\_Parser

String parser

```
public static TextParser<RonString> String_Parser
```

Field Value

TextParser<[RonString](#)>

# Enum UnsignedPrefix

Namespace: [RonCS.AST](#)

Assembly: RonCS.dll

Prefix for unsigned number, indicating the base.

```
public enum UnsignedPrefix
```

## Extension Methods

[TypeConversionExtensions.RonConvert\(object, Type\)](#) ,  
[TypeConversionExtensions.RonConvert<T>\(object\)](#)

## Fields

binary = 2

0b

hex = 16

0x

octal = 8

0o

# Namespace RonCS.Converters

## Classes

### [TupleFunctionConverter](#)

Type converter for a function that returns a tuple.

### [TupleMethodConverter](#)

Type converter for a method that returns a tuple.

### [TuplePropertyConverter](#)

Type converter for a property that returns a tuple.

# Class TupleFunctionConverter

Namespace: [RonCS.Converters](#)

Assembly: RonCS.dll

Type converter for a function that returns a tuple.

```
public class TupleFunctionConverter : TypeSerializerConverter
```

## Inheritance

[object](#)  ← TupleFunctionConverter

## Implements

[TypeSerializerConverter](#)

## Inherited Members

[object.Equals\(object\)](#)  , [object.Equals\(object, object\)](#)  , [object.GetHashCode\(\)](#)  ,  
[object.GetType\(\)](#)  , [object.MemberwiseClone\(\)](#)  , [object.ReferenceEquals\(object, object\)](#)  ,  
[object.ToString\(\)](#) 

## Extension Methods

[TypeConversionExtensions.RonConvert\(object, Type\)](#) ,  
[TypeConversionExtensions.RonConvert<T>\(object\)](#)

# Constructors

## TupleFunctionConverter(string, Func<object, object[]>)

Type converter for a function that returns a tuple.

```
public TupleFunctionConverter(string name, Func<object, object[]> converter)
```

## Parameters

name [string](#) 

converter [Func](#)  <[object](#)  , [object](#)  []>

# Methods

## ToAST(SerializationContext, object)

Convert the source object to an AST node.

```
public RonElement ToAST(SerializationContext context, object source)
```

### Parameters

context [SerializationContext](#)

source [object](#)

### Returns

[RonElement](#)

# Class TupleMethodConverter

Namespace: [RonCS.Converters](#)

Assembly: RonCS.dll

Type converter for a method that returns a tuple.

```
public class TupleMethodConverter : TypeSerializerConverter
```

## Inheritance

[object](#)  ← TupleMethodConverter

## Implements

[TypeSerializerConverter](#)

## Inherited Members

[object.Equals\(object\)](#)  , [object.Equals\(object, object\)](#)  , [object.GetHashCode\(\)](#)  ,  
[object.GetType\(\)](#)  , [object.MemberwiseClone\(\)](#)  , [object.ReferenceEquals\(object, object\)](#)  ,  
[object.ToString\(\)](#) 

## Extension Methods

[TypeConversionExtensions.RonConvert\(object, Type\)](#) ,  
[TypeConversionExtensions.RonConvert<T>\(object\)](#)

# Constructors

## TupleMethodConverter(string, MethodInfo)

Type converter for a method that returns a tuple.

```
public TupleMethodConverter(string name, MethodInfo method)
```

## Parameters

name [string](#) 

method [MethodInfo](#) 

# Methods

## ToAST(SerializationContext, object)

Convert the source object to an AST node.

```
public RonElement ToAST(SerializationContext context, object source)
```

### Parameters

context [SerializationContext](#)

source [object](#)

### Returns

[RonElement](#)

# Class TuplePropertyConverter

Namespace: [RonCS.Converters](#)

Assembly: RonCS.dll

Type converter for a property that returns a tuple.

```
public class TuplePropertyConverter : TypeSerializerConverter
```

## Inheritance

[object](#)  ← TuplePropertyConverter

## Implements

[TypeSerializerConverter](#)

## Inherited Members

[object.Equals\(object\)](#)  , [object.Equals\(object, object\)](#)  , [object.GetHashCode\(\)](#)  ,  
[object.GetType\(\)](#)  , [object.MemberwiseClone\(\)](#)  , [object.ReferenceEquals\(object, object\)](#)  ,  
[object.ToString\(\)](#) 

## Extension Methods

[TypeConversionExtensions.RonConvert\(object, Type\)](#) ,  
[TypeConversionExtensions.RonConvert<T>\(object\)](#)

# Constructors

## TuplePropertyConverter(string, PropertyInfo)

Type converter for a property that returns a tuple.

```
public TuplePropertyConverter(string name, PropertyInfo property)
```

## Parameters

name [string](#) 

property [PropertyInfo](#) 

# Methods

## ToAST(SerializationContext, object)

Convert the source object to an AST node.

```
public RonElement ToAST(SerializationContext context, object source)
```

### Parameters

context [SerializationContext](#)

source [object](#)

### Returns

[RonElement](#)

# Namespace RonCS.Exceptions

## Classes

### [DeserializationException](#)

Ron document failed to deserialize.

### [DeserializationExceptionReason](#)

Reason why a document failed to deserialize.

### [LexerException](#)

Ron document failed to be lexed.

### [NoDictionaryConstructorException](#)

Indicates that the type could not be initialized because it does not have a constructor with a dictionary type argument.

### [NoEmptyConstructorException](#)

Deserialized object could not be constructed because there is no parameterless constructor.

### [NoFieldOrPropertyException](#)

Indicates that a document failed to deserialize because the source type does not have the specified field.

### [NotImplementedForArgumentTypeException](#)

Could not call the specified method because it does not exist on the type.

### [RonException](#)

Base class for ron exceptions.

### [RonParseException](#)

Ron document failed to be parsed.

### [UnknownEnumException](#)

Exception for when an enum case was unknown.

### [UnknownEnumException<T>](#)

Exception for when an enum case was unknown.

# Class DeserializationException

Namespace: [RonCS.Exceptions](#)

Assembly: RonCS.dll

Ron document failed to deserialize.

```
public class DeserializationException : Exception, ISerializable
```

## Inheritance

[object](#) ← [Exception](#) ← DeserializationException

## Implements

[ISerializable](#)

## Inherited Members

[Exception.GetBaseException\(\)](#) , [Exception.GetType\(\)](#) , [Exception.ToString\(\)](#) , [Exception.Data](#) , [Exception.HelpLink](#) , [Exception.HResult](#) , [Exception.InnerException](#) , [Exception.Message](#) , [Exception.Source](#) , [Exception.StackTrace](#) , [Exception.TargetSite](#) , [Exception.SerializeObjectState](#) , [object.Equals\(object\)](#) , [object.Equals\(object, object\)](#) , [object.GetHashCode\(\)](#) , [object.MemberwiseClone\(\)](#) , [object.ReferenceEquals\(object, object\)](#)

## Extension Methods

[TypeConversionExtensions.RonConvert\(object, Type\)](#) ,  
[TypeConversionExtensions.RonConvert<T>\(object\)](#)

## Constructors

DeserializationException(params  
DeserializationExceptionReason[])

Ron document failed to deserialize.

```
public DeserializationException(params DeserializationExceptionReason[] reasons)
```

## Parameters

**reasons** [DeserializationExceptionReason\[\]](#)

# Fields

## Reasons

The reasons why the document failed to deserialize.

```
public readonly IEnumerable<DeserializationExceptionReason> Reasons
```

## Field Value

[IEnumerable](#) <[DeserializationExceptionReason](#)>

# Methods

## FromOthers(IEnumerable<Exception>)

TODO: What does this do?

```
public static DeserializationException FromOthers(IEnumerable<Exception> others)
```

## Parameters

**others** [IEnumerable](#) <[Exception](#)>

## Returns

[DeserializationException](#)

# Class DeserializationExceptionReason

Namespace: [RonCS.Exceptions](#)

Assembly: RonCS.dll

Reason why a document failed to deserialize.

```
public abstract class DeserializationExceptionReason
```

## Inheritance

[object](#)  ← DeserializationExceptionReason

## Derived

[NoFieldOrPropertyException](#)

## Inherited Members

[object.Equals\(object\)](#)  , [object.Equals\(object, object\)](#)  , [object.GetHashCode\(\)](#)  ,  
[object.GetType\(\)](#)  , [object.MemberwiseClone\(\)](#)  , [object.ReferenceEquals\(object, object\)](#)  ,  
[object.ToString\(\)](#) 

## Extension Methods

[TypeConversionExtensions.RonConvert\(object, Type\)](#) ,  
[TypeConversionExtensions.RonConvert<T>\(object\)](#)

# Constructors

## DeserializationExceptionReason(string)

Reason why a document failed to deserialize.

```
protected DeserializationExceptionReason(string ronPath)
```

## Parameters

ronPath [string](#) 

# Fields

## ronPath

The path of the element.

```
public readonly string ronPath
```

## Field Value

[string](#)

## Properties

### Message

Reason message.

```
public abstract string Message { get; }
```

## Property Value

[string](#)

# Class LexerException

Namespace: [RonCS.Exceptions](#)

Assembly: RonCS.dll

Ron document failed to be lexed.

```
public class LexerException : Exception, ISerializable
```

## Inheritance

[object](#)  ← [Exception](#)  ← LexerException

## Implements

[ISerializable](#) 

## Inherited Members

[Exception.GetBaseException\(\)](#)  , [Exception.GetType\(\)](#)  , [Exception.ToString\(\)](#)  , [Exception.Data](#)  , [Exception.HelpLink](#)  , [Exception.HResult](#)  , [Exception.InnerException](#)  , [Exception.Message](#)  , [Exception.Source](#)  , [Exception.StackTrace](#)  , [Exception.TargetSite](#)  , [Exception.SerializeObjectState](#)  , [object.Equals\(object\)](#)  , [object.Equals\(object, object\)](#)  , [object.GetHashCode\(\)](#)  , [object.MemberwiseClone\(\)](#)  , [object.ReferenceEquals\(object, object\)](#) 

## Extension Methods

[TypeConversionExtensions.RonConvert\(object, Type\)](#)  ,  
[TypeConversionExtensions.RonConvert<T>\(object\)](#) 

## Constructors

LexerException(Result<TokenList<RonTokenKind>>)

Ron document failed to be lexed.

```
public LexerException(Result<TokenList<RonTokenKind>> errorResult)
```

## Parameters

**errorResult** Result<TokenList<[RonTokenKind](#)>>

# Fields

## errorResult

The superpower error.

```
public readonly Result<TokenList<RonTokenKind>> errorResult
```

## Field Value

Result<TokenList<[RonTokenKind](#)>>

# Class NoDictionaryConstructorException

Namespace: [RonCS.Exceptions](#)

Assembly: RonCS.dll

Indicates that the type could not be initialized because it does not have a constructor with a dictionary type argument.

```
public class NoDictionaryConstructorException : Exception, ISerializable
```

## Inheritance

[object](#)  ← [Exception](#)  ← NoDictionaryConstructorException

## Implements

[ISerializable](#) 

## Inherited Members

[Exception.GetBaseException\(\)](#)  , [Exception.GetType\(\)](#)  , [Exception.ToString\(\)](#)  , [Exception.Data](#)  , [Exception.HelpLink](#)  , [Exception.HResult](#)  , [Exception.InnerException](#)  , [Exception.Source](#)  , [Exception.StackTrace](#)  , [Exception.TargetSite](#)  , [Exception.SerializeObjectState](#)  , [object.Equals\(object\)](#)  , [object.Equals\(object, object\)](#)  , [object.GetHashCode\(\)](#)  , [object.MemberwiseClone\(\)](#)  , [object.ReferenceEquals\(object, object\)](#) 

## Extension Methods

[TypeConversionExtensions.RonConvert\(object, Type\)](#) ,  
[TypeConversionExtensions.RonConvert<T>\(object\)](#)

## Constructors

### NoDictionaryConstructorException(Type)

Indicates that the type could not be initialized because it does not have a constructor with a dictionary type argument.

```
public NoDictionaryConstructorException(Type type)
```

## Parameters

type [Type](#)

## Properties

### Message

Gets a message that describes the current exception.

```
public override string Message { get; }
```

### Property Value

[string](#)

The error message that explains the reason for the exception, or an empty string ("").

# Class NoEmptyConstructorException

Namespace: [RonCS.Exceptions](#)

Assembly: RonCS.dll

Deserialized object could not be constructed because there is no parameterless constructor.

```
public class NoEmptyConstructorException : Exception, ISerializable
```

## Inheritance

[object](#)  ← [Exception](#)  ← NoEmptyConstructorException

## Implements

[ISerializable](#) 

## Inherited Members

[Exception.GetBaseException\(\)](#)  , [Exception.GetType\(\)](#)  , [Exception.ToString\(\)](#)  , [Exception.Data](#)  , [Exception.HelpLink](#)  , [Exception.HResult](#)  , [Exception.InnerException](#)  , [Exception.Source](#)  , [Exception.StackTrace](#)  , [Exception.TargetSite](#)  , [Exception.SerializeObjectState](#)  , [object.Equals\(object\)](#)  , [object.Equals\(object, object\)](#)  , [object.GetHashCode\(\)](#)  , [object.MemberwiseClone\(\)](#)  , [object.ReferenceEquals\(object, object\)](#) 

## Extension Methods

[TypeConversionExtensions.RonConvert\(object, Type\)](#) ,  
[TypeConversionExtensions.RonConvert<T>\(object\)](#)

## Constructors

### NoEmptyConstructorException(Type)

Deserialized object could not be constructed because there is no parameterless constructor.

```
public NoEmptyConstructorException(Type type)
```

## Parameters

type [Type](#) 

# Properties

## Message

Gets a message that describes the current exception.

```
public override string Message { get; }
```

## Property Value

[string](#)

The error message that explains the reason for the exception, or an empty string ("").

# Class NoFieldOrPropertyException

Namespace: [RonCS.Exceptions](#)

Assembly: RonCS.dll

Indicates that a document failed to deserialize because the source type does not have the specified field.

```
public class NoFieldOrPropertyException : DeserializationExceptionReason
```

## Inheritance

[object](#)  ← [DeserializationExceptionReason](#) ← NoFieldOrPropertyException

## Inherited Members

[DeserializationExceptionReason.ronPath](#) , [object.Equals\(object\)](#)  , [object.Equals\(object, object\)](#)  , [object.GetHashCode\(\)](#)  , [object.GetType\(\)](#)  , [object.MemberwiseClone\(\)](#)  , [object.ReferenceEquals\(object, object\)](#)  , [object.ToString\(\)](#) 

## Extension Methods

[TypeConversionExtensions.RonConvert\(object, Type\)](#) ,  
[TypeConversionExtensions.RonConvert<T>\(object\)](#)

## Constructors

### NoFieldOrPropertyException(string, Type, string)

Indicates that a document failed to deserialize because the source type does not have the specified field.

```
public NoFieldOrPropertyException(string ronPath, Type deserializedType,  
string fieldName)
```

## Parameters

ronPath [string](#) 

deserializedType [Type](#) 

fieldName [string](#) 

# Properties

## Message

Reason message.

```
public override string Message { get; }
```

## Property Value

[string](#) 

# Class

## NotImplementedForArgumentTypeException

Namespace: [RonCS.Exceptions](#)

Assembly: RonCS.dll

Could not call the specified method because it does not exist on the type.

```
public class NotImplementedForArgumentTypeException : Exception, ISerializable
```

### Inheritance

[object](#)  ← [Exception](#)  ← NotImplementedForArgumentTypeException

### Implements

[ISerializable](#) 

### Inherited Members

[Exception.GetBaseException\(\)](#) , [Exception.GetType\(\)](#) , [Exception.ToString\(\)](#) , [Exception.Data](#) , [Exception.HelpLink](#) , [Exception.HResult](#) , [Exception.InnerException](#) , [Exception.Source](#) , [Exception.StackTrace](#) , [Exception.TargetSite](#) , [Exception.SerializeObjectState](#) , [object.Equals\(object\)](#) , [object.Equals\(object, object\)](#) , [object.GetHashCode\(\)](#) , [object.MemberwiseClone\(\)](#) , [object.ReferenceEquals\(object, object\)](#) 

### Extension Methods

[TypeConversionExtensions.RonConvert\(object, Type\)](#) ,  
[TypeConversionExtensions.RonConvert<T>\(object\)](#) 

## Constructors

### NotImplementedForArgumentTypeException(string, Type)

Could not call the specified method because it does not exist on the type.

```
public NotImplementedForArgumentTypeException(string methodName, Type type)
```

### Parameters

**methodName** [string](#) 

type [Type](#)

## Properties

### Message

Gets a message that describes the current exception.

```
public override string Message { get; }
```

### Property Value

[string](#)

The error message that explains the reason for the exception, or an empty string ("").

# Class RonException

Namespace: [RonCS.Exceptions](#)

Assembly: RonCS.dll

Base class for ron exceptions.

```
public static class RonException
```

## Inheritance

[object](#)  ← RonException

## Inherited Members

[object.Equals\(object\)](#)  , [object.Equals\(object, object\)](#)  , [object.GetHashCode\(\)](#)  ,  
[object.GetType\(\)](#)  , [object.MemberwiseClone\(\)](#)  , [object.ReferenceEquals\(object, object\)](#)  ,  
[object.ToString\(\)](#) 

# Class RonParseException

Namespace: [RonCS.Exceptions](#)

Assembly: RonCS.dll

Ron document failed to be parsed.

```
public class RonParseException : Exception, ISerializable
```

## Inheritance

[object](#)  ← [Exception](#)  ← RonParseException

## Implements

[ISerializable](#) 

## Inherited Members

[Exception.GetBaseException\(\)](#)  , [Exception.GetType\(\)](#)  , [Exception.ToString\(\)](#)  , [Exception.Data](#)  , [Exception.HelpLink](#)  , [Exception.HResult](#)  , [Exception.InnerException](#)  , [Exception.Message](#)  , [Exception.Source](#)  , [Exception.StackTrace](#)  , [Exception.TargetSite](#)  , [Exception.SerializeObjectState](#)  , [object.Equals\(object\)](#)  , [object.Equals\(object, object\)](#)  , [object.GetHashCode\(\)](#)  , [object.MemberwiseClone\(\)](#)  , [object.ReferenceEquals\(object, object\)](#) 

## Extension Methods

[TypeConversionExtensions.RonConvert\(object, Type\)](#) ,  
[TypeConversionExtensions.RonConvert<T>\(object\)](#)

## Constructors

RonParseException(TokenListParserResult<RonTokenKind, RonDocument>)

Ron document failed to be parsed.

```
public RonParseException(TokenListParserResult<RonTokenKind, RonDocument> result)
```

## Parameters

**result** TokenListParserResult<[RonTokenKind](#), [RonDocument](#)>

# Fields

## Result

Superpower parser result.

```
public readonly TokenListParserResult<RonTokenKind, RonDocument> Result
```

## Field Value

TokenListParserResult<[RonTokenKind](#), [RonDocument](#)>

# Class UnknownEnumException

Namespace: [RonCS.Exceptions](#)

Assembly: RonCS.dll

Exception for when an enum case was unknown.

```
public class UnknownEnumException
```

## Inheritance

[object](#)  ← UnknownEnumException

## Inherited Members

[object.Equals\(object\)](#)  , [object.Equals\(object, object\)](#)  , [object.GetHashCode\(\)](#)  ,  
[object.GetType\(\)](#)  , [object.MemberwiseClone\(\)](#)  , [object.ReferenceEquals\(object, object\)](#)  ,  
[object.ToString\(\)](#) 

## Extension Methods

[TypeConversionExtensions.RonConvert\(object, Type\)](#) ,  
[TypeConversionExtensions.RonConvert<T>\(object\)](#)

# Class UnknownEnumException<T>

Namespace: [RonCS.Exceptions](#)

Assembly: RonCS.dll

Exception for when an enum case was unknown.

```
public class UnknownEnumException<T> : Exception, ISerializable
```

## Type Parameters

**T**

### Inheritance

[object](#)  ← [Exception](#)  ← UnknownEnumException<T>

### Implements

[ISerializable](#) 

### Inherited Members

[Exception.GetBaseException\(\)](#)  , [Exception.GetType\(\)](#)  , [Exception.ToString\(\)](#)  , [Exception.Data](#)  , [Exception.HelpLink](#)  , [Exception.HResult](#)  , [Exception.InnerException](#)  , [Exception.Source](#)  , [Exception.StackTrace](#)  , [Exception.TargetSite](#)  , [Exception.SerializeObjectState](#)  , [object.Equals\(object\)](#)  , [object.Equals\(object, object\)](#)  , [object.GetHashCode\(\)](#)  , [object.MemberwiseClone\(\)](#)  , [object.ReferenceEquals\(object, object\)](#) 

### Extension Methods

[TypeConversionExtensions.RonConvert\(object, Type\)](#) ,  
[TypeConversionExtensions.RonConvert<T>\(object\)](#)

## Constructors

### UnknownEnumException(T?)

Exception for when an enum case was unknown.

```
public UnknownEnumException(T? value)
```

## Parameters

value T

# Properties

## Message

Gets a message that describes the current exception.

```
public override string Message { get; }
```

## Property Value

[string](#)

The error message that explains the reason for the exception, or an empty string ("").