


Enrutamiento

Enrutamiento se usa para que dos redes con dos rúters diferentes se puedan comunicar entre si, para hacer lo posible lo separamos en tres subredes, el azul, verde y el rojo son su subred propio y conectados entre ellos con STATIC enrutamiento



Copiar esta Red primero

Azul con IP: 192.168.0.0 /18 = 255.255.192.0

Verde con IP: 192.168.64.0 /18 = 255.255.192.0

Rojo con IP: 192.168.128.0 /18 = 255.255.192.0

Ya sabemos como conectar como conectar un PC con un switch y su router pero al final podre todos los IPs por si se olvida algo

Subred Izquierda

PC0 tiene la configuración IP:

IPv4: 192.168.0.2

Subnet mask: 255.255.192.0

Default Gateway: 192.168.0.1 (Router IP)

PC1 tiene la configuración IP:

IPv4: 192.168.0.3

Subnet mask: 255.255.192.0

Default Gateway: 192.168.0.1


Subred Central

Router0 tiene la configuración IP:

Giga 0/0/0 = 192.168.0.1

Giga 0/0/1 = 192.168.128.1

STATIC



192.168.64.0/18 via 192.168.128.2

Como hacer la Regla STATIC

Network: Donde quiero ir? Quiero ir desde 192.168.0.0 a 192.168.64.0 entonces ponemos 192.168.64.0

Mascara: Usamos la mascara del destino entonces /18 = 255.255.192.0

Next Hop: Ahora en la Subred roja nos tenemos que fijar, usamos el IP del destino entonces si Router0 es 192.168.128.1

Router1 seria 192.168.128.2

y le damos a aplicar y ya estaríamos

La del Router1 seria

Network: 192.168.0.0

Mascara: 255.255.192.0

Next hop: 192.168.128.1

Subred Derecha

PC2 tiene la configuración IP:

IPv4: 192.168.64.3

Subnet mask: 255.255.192.0

Default Gateway: 192.168.64.1 (Router IP)


Laptop0 tiene la configuración IP:

IPv4: 192.168.64.2


Subnet mask: 255.255.192.0

Default Gateway: 192.168.64.1

PC0



PC1



Router0

Router0

Physical **Config** CLI Attributes

GLOBAL

Settings

Algorithm Settings

ROUTING

Static

RIP

SWITCHING

VLAN Database

INTERFACE

GigabitEthernet0/0/0

GigabitEthernet0/0/1

GigabitEthernet0/0/2

GigabitEthernet0/0/0

Port Status ☒ On

Link Speed 1000 Mbps 100 Mbps 10 Mbps ☒ Auto

Duplex Half Duplex Full Duplex ☒ Auto

MAC Address 000A.4194.BD01

IP Configuration

IPv4 Address 192.168.0.1

Subnet Mask 255.255.192.0

Tx Ring Limit 10

Router0

Physical **Config** CLI Attributes

GLOBAL

Settings

Algorithm Settings

ROUTING

Static

RIP

SWITCHING

VLAN Database

INTERFACE

GigabitEthernet0/0/0

GigabitEthernet0/0/1

GigabitEthernet0/0/2

GigabitEthernet0/0/1

Port Status ☒ On

Link Speed 1000 Mbps 100 Mbps 10 Mbps ☒ Auto

Duplex Half Duplex Full Duplex ☒ Auto

MAC Address 000A.4194.BD02

IP Configuration

IPv4 Address 192.168.128.1

Subnet Mask 255.255.192.0

Tx Ring Limit 10

Router1

Router1

Physical **Config** CLI Attributes

GLOBAL

Settings

Algorithm Settings

ROUTING

Static

RIP

SWITCHING

VLAN Database

INTERFACE

GigabitEthernet0/0/0

GigabitEthernet0/0/1

GigabitEthernet0/0/2

GigabitEthernet0/0/0

Port Status ☒ On

Link Speed 1000 Mbps 100 Mbps 10 Mbps ☒ Auto

Duplex Half Duplex Full Duplex ☒ Auto


MAC Address 0001.43D2.3B01

IP Configuration


IPv4 Address 192.168.128.2

Subnet Mask 255.255.192.0

Tx Ring Limit 10



PC2



Laptop0

