

BUILD YOUR AI CEO — THE COMPLETE SETUP GUIDE

Discord Setup Checklist

Build Your AI CEO: The Complete Setup Guide

MODULE 3 — DOWNLOAD PACKET

Control Room Setup + Bot Permissions Guide

Why Discord?

Discord is your AI CEO's command center. It's where you send instructions, receive briefings, review reports, and monitor everything your system is doing — from any device, anywhere. Once set up, your Discord server becomes the single interface between you and your AI.

Pre-Setup Checklist

Before you begin, make sure you have:

- ☐ A Discord account (free at discord.com)
 - ☐ Discord installed on your computer and phone
 - ☐ Access to the Discord Developer Portal (discord.com/developers)
 - ☐ Your OpenClaw API key ready (from the API Key Setup Checklist)
 - ☐ About 30–45 minutes to complete the full setup
-

Part 1: Create Your Discord Server

This will be your private AI control room — not a public community server.

1. Open Discord
2. Click the + icon in the left sidebar (below your existing servers)
3. Select **"Create My Own"**
4. Select **"For me and my friends"** (keeps it private)

5. Name your server — suggested name: `[Your AI's Name] HQ` (e.g., `Cyrus HQ`)
6. Click **"Create"**

Your server is now created. You'll see a default `#general` channel — you can keep or delete it.

Part 2: Create Your Required Channels

You need 6 specific channels in your server. Each one has a dedicated purpose.

For each channel:

1. Click the **+** next to "TEXT CHANNELS" in the left sidebar
2. Select **"Text Channel"**
3. Enter the channel name exactly as shown below
4. Click **"Create Channel"**

Required Channels

Channel Name	Purpose
<code>#operator</code>	Your main control channel. This is where you send messages to your AI and receive its responses. Think of it as your private command line.
<code>#morning-brief</code>	Your AI posts its daily morning briefing here every morning — priorities, open tasks, and what to focus on today.
<code>#bugs</code>	Errors, failed tasks, and system issues get logged here automatically. Check this channel if something seems off.
<code>#content</code>	Content ideas, draft scripts, social post suggestions, and content planning output from your AI.
<code>#strategy</code>	Venture proposals, market research summaries, strategic recommendations, and board meeting outputs.
<code>#nightly-review</code>	Your AI's nightly summary: what happened today, memory updates, tasks completed, and tomorrow's setup.

After creating all 6, your channel list should look like:

TEXT CHANNELS

- # operator
- # morning-brief
- # bugs
- # content
- # strategy
- # nightly-review

Part 3: Create Your Discord Bot

Your bot is the technical bridge between OpenClaw and your Discord server. Here's how to create it.

Step 1 — Open the Developer Portal

1. Go to discord.com/developers/applications
2. Log in with your Discord account if prompted
3. Click **"New Application"** (top right)
4. Name your application — e.g., or
5. Accept the terms and click **"Create"**

Step 2 — Configure the Bot

1. In the left sidebar, click **"Bot"**
2. Click **"Add Bot"** → Confirm with **"Yes, do it!"**
3. Set your bot's username — use your AI's name (e.g.,)
4. Optional: upload a profile picture for your bot

Step 3 — Copy Your Bot Token

 *This token is a sensitive secret — treat it exactly like an API key.*

1. Under the Bot section, click **"Reset Token"** (or "Copy" if already visible)
2. Confirm the action if prompted
3. **Immediately copy the token** — it looks like:
4. Save it temporarily in a secure location (you'll add it to your OpenClaw config)

- ☐ Bot token copied and stored securely

Step 4 — Enable Required Intents

Still on the Bot page, scroll down to **"Privileged Gateway Intents"**:

- ☐ Enable **"Server Members Intent"**
- ☐ Enable **"Message Content Intent"**

Click **"Save Changes"**.

Part 4: Required Bot Permissions

Your bot needs the following permissions to function properly. Here's what each one does and why it's needed:

Permission	Why It's Needed
Send Messages	Your AI needs to post messages in channels — briefings, reports, and responses
Read Message History	Your AI needs to read previous messages to understand conversation context
Embed Links	Allows your AI to send formatted rich messages with structured layouts
Attach Files	Allows your AI to share documents, reports, and files directly in Discord
View Channels	Your AI must be able to see the channels it operates in
Use Application Commands	Enables slash command functionality for advanced interactions
Add Reactions	Allows your AI to react to messages as confirmation signals
Manage Messages	Allows your AI to clean up or pin important messages when needed

Part 5: Generate the Invite URL and Add Bot to Your Server

Step 1 — Go to OAuth2

1. In the Developer Portal, click **"OAuth2"** in the left sidebar
2. Click **"URL Generator"**

Step 2 — Select Scopes

Under "Scopes," check:

- ☐ bot
- ☐ applications.commands

Step 3 — Select Bot Permissions

Under "Bot Permissions," check all permissions from the list in Part 4:

- ☐ Send Messages
- ☐ Read Message History
- ☐ Embed Links
- ☐ Attach Files
- ☐ View Channels
- ☐ Use Application Commands
- ☐ Add Reactions
- ☐ Manage Messages

Step 4 — Copy and Use the Generated URL

1. Scroll down — you'll see a "**Generated URL**" at the bottom of the page
2. Copy this URL
3. Paste it into a new browser tab
4. Select your server from the dropdown (e.g., `Cyrus HQ`)
5. Click "**Authorize**"
6. Complete any CAPTCHA if prompted

Your bot is now in your server. You should see it appear in the Members list on the right side of Discord, initially shown as offline.

- ☐ Bot visible in server member list

Part 6: Find and Copy Your Server ID and Channel IDs

You need these IDs for your OpenClaw configuration file.

Enable Developer Mode

1. In Discord, click **User Settings** (gear icon, bottom left)
2. Go to **Advanced**
3. Toggle "**Developer Mode**" to ON
4. Close Settings

Copy Your Server ID

1. Right-click your server name in the left sidebar
2. Click "**Copy Server ID**"
3. Paste it somewhere safe — you'll add it to `openclaw.json`

☐ Server ID copied

Copy Each Channel ID

For each of your 6 channels:

1. Right-click the channel name (e.g., `#operator`)
2. Click "**Copy Channel ID**"
3. Label it and save it — e.g., `operator channel: 1234567890123456001`

☐ #operator ID copied

☐ #morning-brief ID copied

☐ #bugs ID copied

☐ #content ID copied

☐ #strategy ID copied

☐ #nightly-review ID copied

Part 7: Verification Checklist

After completing setup, confirm your bot is connected and working:

Connection Check

- ☐ Bot appears in your server's member list
- ☐ Bot shows as **online** after OpenClaw is started (it may show offline until OpenClaw runs)

Functionality Check

Once OpenClaw is running:

1. Go to your `#operator` channel
 2. Type a simple message — e.g., `Hello`
 3. Your AI should respond within a few seconds
- ☐ AI responds to a message in #operator
 - ☐ Message appears correctly formatted
 - ☐ Response comes through in under 10 seconds

Channel Check

Send these test messages to verify each channel is accessible:

- ☐ Post a test message in `#morning-brief` — confirm it appears
 - ☐ Post a test message in `#strategy` — confirm it appears
-

Troubleshooting

Bot is not responding in any channel

Check 1: Is OpenClaw running?

```
▷  TERMINAL COMMAND — COPY & PASTE INTO TERMINAL

openclaw gateway status
```

If not running:

```
▷  TERMINAL COMMAND — COPY & PASTE INTO TERMINAL

openclaw gateway restart
```

Check 2: Is your bot token correct in `openclaw.json` ?

Open your config and verify the token matches what's in the Developer Portal.

Check 3: Is the bot online in your server?

If the bot is shown as "offline" in your member list, OpenClaw is not connected to Discord. Restart OpenClaw.

Bot is responding but in the wrong channel

Cause: Channel IDs in your `openclaw.json` may be assigned incorrectly.

Fix:

1. Right-click each channel to re-copy its ID
 2. Update the corresponding field in your `openclaw.json`
 3. Run `openclaw gateway restart`
-

Bot is in the server but has no permissions

Cause: The permissions were not selected correctly when generating the OAuth2 URL.

Fix:

1. Return to the OAuth2 URL Generator in the Developer Portal
 2. Re-select all required permissions
 3. Generate a new URL and use it to re-authorize the bot to your server
 4. The bot will update its permissions automatically
-

"Missing Access" errors in OpenClaw logs

Cause: The bot can't access one or more channels.

Fix:

1. In Discord, right-click the problem channel
 2. Click **Edit Channel** → **Permissions**
 3. Click the + to add your bot
 4. Grant it View Channel, Send Messages, and Read Message History
 5. Save
-

Bot token "invalid" error

Cause: The token was not copied correctly, has been reset, or contains extra spaces.

Fix:

1. In the Developer Portal → Your Application → Bot
 2. Click **"Reset Token"** to generate a fresh one
 3. Copy carefully — no extra spaces
 4. Update `openclaw.json` with the new token
 5. Restart OpenClaw
-

Final Setup Summary

You should now have:

- ☐ Discord server created with 6 channels
- ☐ Bot application created in Discord Developer Portal
- ☐ Bot token saved to `openclaw.json`
- ☐ Server ID saved to `openclaw.json`
- ☐ All 6 channel IDs saved to `openclaw.json`
- ☐ Bot successfully invited to your server with full permissions
- ☐ Developer Mode enabled

🟡 AI responding in `#operator`

Your Discord control room is live. Your AI CEO has a voice.

Build Your AI CEO: The Complete Setup Guide — cyrushq.ai

BUILD YOUR AI CEO

cyrushq.ai