


EC2

1. Login to AWS Management Console.



2. **Select your preferred Region.** Select a region from the drop-down, the selection of the region can be done on the basis of the criteria discussed earlier in the blog.

Edureka
Oregon
Support

US East (N. Virginia)
US West (N. California)
US West (Oregon)
EU (Ireland)
EU (Frankfurt)
Asia Pacific (Tokyo)
Asia Pacific (Seoul)
Asia Pacific (Singapore)
Asia Pacific (Sydney)
Asia Pacific (Mumbai)
South America (São Paulo)

Learn more

ction of

r more tags.

object,

t in your

Tag Editor

ES

r view our

t AWS.

pp

3. **Select EC2 Service** Click EC2 under Compute section. This will take you to the EC2 dashboard.

Amazon Web Services

Compute


EC2
Virtual Servers in the Cloud


EC2 Container Service
Run and Manage Docker Containers



Elastic Beanstalk
Run and Manage Web Apps


Lambda
Run Code without Thinking about Servers

4. Click **Launch Instance**.

5. **Select an AMI:** because you require a Linux instance, in the row for the basic 64-bit Ubuntu AMI, click Select.


Ubuntu Server 14.04 LTS (HVM), SSD Volume Type - ami-d732f0b7
Select



Ubuntu Server 14.04 LTS (HVM), EBS General Purpose (SSD) Volume Type. Support available from Canonical (<http://www.ubuntu.com/cloud/services>).
 Root device type: ebs Virtualization type: hvm

64-bit

6. Choose an Instance

Select t2.micro instance, which is free tier eligible.

Step 2: Choose an Instance Type

	Family	Type	vCPUs	Memory (GiB)	Instance Storage (GB)
☐	General purpose	t2.nano	1	0.5	EBS only
☒	General purpose	t2.micro Free tier eligible	1	1	EBS only

7. Configure Instance Details.

Configure all the details and then click on add storage

Press enter or click to view image in full size

Step 3: Configure Instance Details

Number of instances i

Launch into Auto Scaling Group i

Purchasing option i
☐ Request Spot instances

Network i

Create new VPC

Subnet i

Create new subnet

245 IP Addresses available

Auto-assign Public IP i

IAM role i

Create new IAM role

Cancel
Previous
Review and Launch
Next: Add Storage

8. Add Storage

Press enter or click to view image in full size

Step 4: Add Storage

Volume Type i	Device i	Snapshot i	Size (GiB) i	Volume Type i	IOPS i
Root	/dev/sda1	snap-47713105	8	General Purpose SSD (GP2) ▼	100 / 3000
Add New Volume Cancel Previous Review and Launch Next: Tag Instance					

9. Tag an Instance

Type a name for your AWS EC2 instance in the value box. This name, more correctly known as a tag, will appear in the console when the instance launches. It makes it easy to keep track of running machines in a complex environment. Use a name that you can easily recognize and remember.

Press enter or click to view image in full size

Step 5: Tag Instance

Key (127 characters maximum)	Value (255 characters maximum)
Name	ec21-linux
Create Tag (Up to 50 tags maximum) Cancel Previous Review and Launch Next: Configure Security Group	

10. Create a Security Group

Press enter or click to view image in full size

Step 6: Configure Security Group

Assign a security group: ☒ Create a new security group

☐ Select an existing security group

Security group name:	launch-wizard-15
Description:	launch-wizard-15 created 2016-10-12T18:31:14.820+05:30

Type i	Protocol i	Port Range i
SSH ▼	TCP	22
Add Rule Cancel Previous Review and Launch		

11. Review and Launch an Instance

Verify the details that you have configured to launch an instance.

Press enter or click to view image in full size

Step 7: Review Instance Launch

AMI Details

[Edit AMI](#)

Ubuntu Server 14.04 LTS (HVM), SSD Volume Type - ami-d732f0b7

Free tier
eligible

Ubuntu Server 14.04 LTS (HVM), EBS General Purpose (SSD) Volume Type. Support available from Canonical

Root Device Type: ebs Virtualization type: hvm

Instance Type

[Edit instance type](#)

Instance Type	ECUs	vCPUs	Memory (GiB)	Instance Storage (GB)
t2.micro	Variable	1	1	EBS only

[Cancel](#)[Previous](#)[Launch](#)

12. Create a Key Pair & launch an Instance

Next, in this AWS EC2 Tutorial, select the option 'Create a new key pair' and give a name of a key pair. After that, download it in your system and save it for future use.

Select an existing key pair or create a new key pair

A key pair consists of a **public key** that AWS stores, and a **private key file** that you store. Together, they allow you to connect to your instance securely. For Windows AMIs, the private key file is required to obtain the password used to log into your instance. For Linux AMIs, the private key file allows you to securely SSH into your instance.

Note: The selected key pair will be added to the set of keys authorized for this instance. Learn more about [removing existing key pairs from a public AMI](#).

Create a new key pair

Key pair name

edureka_aws

Download Key Pair

You have to download the **private key file** (*.pem file) before you can continue. Store it in a secure and accessible location. You will not be able to download the file again after it's created.

[Cancel](#) [Launch Instances](#)

13. Check the details of a launched instance.

Press enter or click to view image in full size

Launch Instance

Connect

Actions

Filter by tags and attributes or search by keyword

1 to 17 o

☐	Name	Instance ID	Instance Type	Availability Zone	Instance State	Status Checks
☐	WPS Instance	i-89bf6251	m4.large	us-west-2a	running	2/2 checks
☐	Ec21_linux	i-8d263195	t2.micro	us-west-2a	running	2/2 checks
☐	DoNotTouch	i-c43fccc	m1.large	us-west-2b	stopped	

Instances:

i-8226319a (Ec21_linux)


,

i-8326319b (Ec21_linux)

14. Converting Your Private Key Using PuTTYgen

PuTTY does not natively support the private key format (.pem) generated by Amazon EC2. PuTTY has a tool called PuTTYgen, which can convert keys to the required PuTTY format (.ppk). You must convert your private key into this format (.ppk) before attempting to connect to your instance using PuTTY.

- Click Load. By default, PuTTYgen displays only files with the extension .ppk. To locate your .pem file, select the option to display files of all types.




- Select your .pem file for the key pair that you specified when you launch your instance, and then click Open. Click OK to dismiss the confirmation dialog box.


- Click Save private key to save the key in the format that PuTTY can use. PuTTYgen displays a warning about saving the key without a passphrase. Click Yes.
- Specify the same name for the key that you used for the key pair (for example, my-key-pair). PuTTY automatically adds the .ppk file extension.

15. Connect to EC2 instance using SSH and PuTTY

- Open PuTTY.exe
- In the Host Name box, enter Public IP of your instance.
- In the Category list, expand SSH.
- Click Auth (don't expand it).
- In the Private Key file for authentication box, browse to the PPK file that you downloaded and double-click it.
- Click Open.



- Type in Ubuntu when prompted for login ID.

A terminal window titled 'ubuntu@ip-10-253-68-44: ~' with standard window controls. The terminal displays system information, update status, and login details.

```
ubuntu@ip-10-253-68-44: ~  
* Documentation:  https://help.ubuntu.com/  
  
System information as of Fri Sep 30 08:47:04 CEST 2016  
  
System load:  0.0                Processes:            77  
Usage of /:   20.3% of 7.75GB    Users logged in:     0  
Memory usage: 2%                IP address for eth0: 10.253.68.44  
Swap usage:   0%  
  
Graph this data and manage this system at:  
  https://landscape.canonical.com/  
  
Get cloud support with Ubuntu Advantage Cloud Guest:  
  http://www.ubuntu.com/business/services/cloud  
  
302 packages can be updated.  
164 updates are security updates.  
  
*** /dev/xvda1 should be checked for errors ***  
  
Last login: Fri Sep 30 08:47:07 2016 from 27.251.249.218  
ubuntu@ip-10-253-68-44:~$
```

Congratulations! You have launched an Ubuntu Instance successfully.