



Steps To create Auto Scaling Launch Template

Step 1: Click on the All Services on AWS Dashboard


Step 2: Click on the EC2(Elastic Cloud Computing).




Step 3: Scroll Down and click on the Launch Templates and click on the Create launch template




Step 4: Type the Template name.



Step 5: Select the Amazon Machine Image.



Step 6: Select the Instance Type and Key pair.



Step 7: Select the Security Group or Create the new one.

▼ Network settings [Info](#)

Subnet [Info](#)

Don't include in launch template ▼ [Create new subnet](#)

When you specify a subnet, a network interface is automatically added to your template.

Availability Zone [Info](#)

Don't include in launch template ▼ [Enable additional zones](#)

Firewall (security groups) [Info](#)

A security group is a set of firewall rules that control the traffic for your instance. Add rules to allow specific traffic to reach your instance.

☒ Select existing security group ☐ Create security group

Security groups [Info](#)

Select security groups ▼ [Compare security group rules](#)

default sg-06e2ebabcd16ae6f8 ✕
VPC: vpc-034a43ec2832d7f54

Step 8: Click on the Create Launch Template.

▼ Network settings [Info](#)

Subnet [Info](#)

Don't include in launch template ▼ [Create new subnet](#)

When you specify a subnet, a network interface is automatically added to your template.

Availability Zone [Info](#)

Don't include in launch template ▼ [Enable additional zones](#)

Firewall (security groups) [Info](#)

A security group is a set of firewall rules that control the traffic for your instance. Add rules to allow specific traffic to reach your instance.

☒ Select existing security group ☐ Create security group

Security groups [Info](#)

Select security groups ▼ [Compare security group rules](#)

default sg-06e2ebabcd16ae6f8 ✕
VPC: vpc-034a43ec2832d7f54

► Advanced network configuration

▼ Summary

Software Image (AMI)
Amazon Linux 2023 AMI 2023.11...[read more](#)
ami-0236922087fa98b6e

Virtual server type (instance type)
t2.micro

Firewall (security group)
default

Storage (volumes)
1 volume(s) - 8 GiB

[Cancel](#) [Create launch template](#)

Step 9: Now you can see the template is created. Now, scroll down and click on the Auto Scaling Groups.

Launch Templates (1) [Info](#)

[Search](#)


☐	Launch Template ID	Launch Template Name	Default Version	Latest Version	Create Time	Create
☐	lt-01cb184ab77aa182d	my-template	1	1	2026-05-22T08:55:30.000Z	arn:a

Select a launch template


Auto Scaling
Auto Scaling Groups

Create An Auto Scaling Group Using a Launch Template


Step 1: Click on the Create Auto Scaling group.



Step 2: Type the Auto Scaling group name.



Step 3: Select your Template.



Step 4: Select the VPC or go with the default VPC and also select the Availability zone.

Network Info

For most applications, you can use multiple Availability Zones and let EC2 Auto Scaling balance your instances across the zones. The default configuration gets started quickly.

VPC
Choose the VPC that defines the virtual network for your Auto Scaling group.

vpc-034a43ec2832d7f54
172.31.0.0/16 Default

[Create a VPC](#)

Availability Zones and subnets
Define which Availability Zones and subnets your Auto Scaling group can use in the chosen VPC.

Select Availability Zones and subnets

use1-az2 (us-east-1b) | subnet-0b66a455dc2ee1ab3
172.31.80.0/20 Default

use1-az1 (us-east-1a) | subnet-08acb1db903b9def7
172.31.0.0/20 Default

use1-az4 (us-east-1c) | subnet-0abf9a1c06de73450
172.31.16.0/20 Default

[Create a subnet](#)

Step 5: Skip Integrate with other services

Step 6: Configure the Group size and Scaling policies.

Select as per your requirement:

- Desired: 4
- Minimum: 4
- Maximum: 8

Configure group size and scaling - *optional* [Info](#)

Define your group's desired capacity and scaling limits. You can optionally add automatic scaling to adjust the size of your group.

Group size [Info](#)

Set the initial size of the Auto Scaling group. After creating the group, you can change its size to meet demand, either manually or by using automatic scaling.

Desired capacity type

Choose the unit of measurement for the desired capacity value. vCPUs and Memory(GiB) are only supported for mixed instances groups configured with a set of instance types.

Units (number of instances) ▼

Desired capacity

Specify your group size.

4

Scaling [Info](#)

You can resize your Auto Scaling group manually or automatically to meet changes in demand.

Scaling limits

Set limits on how much your desired capacity can be increased or decreased.

Min desired capacity

4

Equal or less than desired capacity

Max desired capacity

8

Equal or greater than desired capacity

Step 7: Select the Target tracking scaling policy.

Automatic scaling - *optional*

Choose whether to use a target tracking policy [Info](#)

You can set up other metric-based scaling policies and scheduled scaling after creating your Auto Scaling group.

☐

No scaling policies

Your Auto Scaling group will remain at its initial size and will not dynamically resize to meet demand.

☒

Target tracking scaling policy

Choose a CloudWatch metric and target value and let the scaling policy adjust the desired capacity in proportion to the metric's value.

Scaling policy name

Target Tracking Policy

Metric type [Info](#)

Monitored metric that determines if resource utilization is too low or high. If using EC2 metrics, consider enabling detailed monitoring for better scaling performance.

Average CPU utilization ▼

Target value

50

Instance warmup [Info](#)

60

seconds

☐ Disable scale in to create only a scale-out policy

Step 8: Click on the Create Auto Scaling Group.

Step 5: Add notifications Edit

Notifications

No notifications

Step 6: Add tags Edit

Tags (0)

Key	Value	Tag new instances
No tags		

Preview code Cancel Previous Create Auto Scaling group

- Now you can see the Auto Scaling is creating and it is also creating the desired state of the EC2 Instance

Auto Scaling groups (1) Info Last updated less than a minute ago Launch configurations Launch templates t2 Actions Create Auto Scaling group

Search your Auto Scaling groups

Name	Status - new	Launch template/configuration t2	Instances	Instance health - new	Desired capacity	Min	Max
my-scaling	Updating capacity	my-template Version Default	0	-	4	4	8

- We selected the Desired state equal to 4 and you can see the 4 Instance is Running

Instances (4) Info Last updated less than a minute ago Connect Instance state Actions Launch instances

Saved filter sets
Choose filter set Find Instance by attribute or tag (case-sensitive)

Instance state = running Clear filters

Name	Instance ID	Instance state	Instance type	Status check	Availability Zone	Public IPv4 DNS	Public IP
	i-02c1d09689b4442df	Running	t2.micro	Initializing	us-east-1c	ec2-98-81-243-81.com...	98.81.243.81
	i-0477ca9c7da887d59	Running	t2.micro	Initializing	us-east-1c	ec2-54-221-43-237.co...	54.221.43.237
	i-0e870aed3c15eb3ff	Running	t2.micro	Initializing	us-east-1b	ec2-100-55-41-16.com...	100.55.41.16
	i-05fc1bfb65c0f061	Running	t2.micro	Initializing	us-east-1a	ec2-3-239-110-131.co...	3.239.110.131