

-- PART 1: DATABASE, USER AND INITIAL SETUP

```
CREATE DATABASE IF NOT EXISTS ridehail_ethiopia
CHARACTER SET utf8mb4 COLLATE utf8mb4_unicode_ci;
CREATE USER IF NOT EXISTS 'ridehail_admin'@'localhost'
IDENTIFIED BY '12345678';
GRANT ALL PRIVILEGES ON ridehail_ethiopia.* TO
'ridehail_admin'@'localhost';
FLUSH PRIVILEGES;
USE ridehail_ethiopia;
SET NAMES utf8mb4;
SET FOREIGN_KEY_CHECKS = 0;
SET SQL_MODE =
'STRICT_TRANS_TABLES,NO_ZERO_IN_DATE,NO_ZERO_DATE,ERROR_FOR_DIVISION_BY_ZERO,NO_ENGINE_SUBSTITUTION';
```

```
CREATE TABLE IF NOT EXISTS cities (
city_id INT NOT NULL AUTO_INCREMENT,
city_name VARCHAR(100) NOT NULL,
region
ENUM('addis_ababa','adama','hawassa','dire_dawa','bahir_dar','mekelle','gondar','jimma','dessie','debre_birhan') NOT NULL,
country_code CHAR(2) NOT NULL DEFAULT 'ET',
latitude DECIMAL(10,8) NOT NULL,
longitude DECIMAL(11,8) NOT NULL,
timezone VARCHAR(50) NOT NULL DEFAULT
'Africa/Addis_Ababa',
population INT DEFAULT NULL,
is_active TINYINT(1) NOT NULL DEFAULT 1,
surge_multiplier_default DECIMAL(4,2) NOT NULL
DEFAULT 1.00,
created_at DATETIME NOT NULL DEFAULT
CURRENT_TIMESTAMP,
updated_at DATETIME NOT NULL DEFAULT
CURRENT_TIMESTAMP ON UPDATE
CURRENT_TIMESTAMP,
```

```
PRIMARY KEY (city_id),  
UNIQUE KEY uq_city_name (city_name)  
) ENGINE=InnoDB;
```

```
CREATE TABLE IF NOT EXISTS zones (  
zone_id INT NOT NULL AUTO_INCREMENT,  
city_id INT NOT NULL,  
zone_name VARCHAR(150) NOT NULL,  
zone_code VARCHAR(20) NOT NULL,  
center_lat DECIMAL(10,8) NOT NULL,  
center_lon DECIMAL(11,8) NOT NULL,  
radius_meters INT NOT NULL DEFAULT 2000,  
base_fare DECIMAL(10,2) NOT NULL DEFAULT 30.00,  
per_km_rate DECIMAL(10,2) NOT NULL DEFAULT 15.00,  
per_minute_rate DECIMAL(10,2) NOT NULL DEFAULT 3.00,  
is_airport_zone TINYINT(1) NOT NULL DEFAULT 0,  
is_active TINYINT(1) NOT NULL DEFAULT 1,  
created_at DATETIME NOT NULL DEFAULT  
CURRENT_TIMESTAMP,  
PRIMARY KEY (zone_id),  
CONSTRAINT fk_zone_city FOREIGN KEY (city_id)  
REFERENCES cities(city_id) ON DELETE CASCADE  
) ENGINE=InnoDB;
```

```
CREATE TABLE IF NOT EXISTS vehicles (  
vehicle_id BIGINT NOT NULL AUTO_INCREMENT,  
make VARCHAR(100) NOT NULL,  
model VARCHAR(100) NOT NULL,  
year SMALLINT NOT NULL,  
color VARCHAR(50) NOT NULL,  
plate_number_hash VARCHAR(64) NOT NULL,  
plate_number_encrypted BLOB NOT NULL,  
vehicle_type ENUM('sedan','minivan','suv','motorcycle','tuk_tuk')  
NOT NULL DEFAULT 'sedan',  
capacity SMALLINT NOT NULL DEFAULT 4,  
is_ac_available TINYINT(1) NOT NULL DEFAULT 0,  
insurance_expiry DATE NOT NULL,
```

```
inspection_expiry DATE NOT NULL,  
is_active TINYINT(1) NOT NULL DEFAULT 1,  
created_at DATETIME NOT NULL DEFAULT  
CURRENT_TIMESTAMP,  
updated_at DATETIME NOT NULL DEFAULT  
CURRENT_TIMESTAMP ON UPDATE  
CURRENT_TIMESTAMP,  
PRIMARY KEY (vehicle_id),  
UNIQUE KEY uq_plate_hash (plate_number_hash)  
) ENGINE=InnoDB;
```

```
CREATE TABLE IF NOT EXISTS promo_codes (  
promo_id BIGINT NOT NULL AUTO_INCREMENT,  
code VARCHAR(50) NOT NULL,  
description TEXT,  
discount_type VARCHAR(20) NOT NULL DEFAULT  
'percentage',  
discount_value DECIMAL(10,2) NOT NULL,  
max_discount_etb DECIMAL(10,2) DEFAULT NULL,  
min_ride_fare DECIMAL(10,2) NOT NULL DEFAULT 0.00,  
usage_limit INT DEFAULT NULL,  
usage_count INT NOT NULL DEFAULT 0,  
per_user_limit INT NOT NULL DEFAULT 1,  
city_id INT DEFAULT NULL,  
valid_from DATETIME NOT NULL,  
valid_until DATETIME NOT NULL,  
is_active TINYINT(1) NOT NULL DEFAULT 1,  
created_at DATETIME NOT NULL DEFAULT  
CURRENT_TIMESTAMP,  
PRIMARY KEY (promo_id),  
UNIQUE KEY uq_promo_code (code),  
CONSTRAINT fk_promo_city FOREIGN KEY (city_id)  
REFERENCES cities(city_id) ON DELETE SET NULL  
) ENGINE=InnoDB;
```