Hydrodynamic model of Conception Bay

This README file contains practical information and background information on the data. The dataset can be cited as:

DHI. (2024). Hydrodynamic model of Conception Bay: MIKE21 model setup, outputs and observation data (1.0) [Data set]. Zenodo. https://doi.org/10.5281/zenodo.14504931

See the license for information on using the data.

Disclaimer:

The included MIKE21 model setup is designed as a simple demonstration for educational and research purposes. It is not optimized for precision or exhaustive calibration and should not be regarded as a benchmark for best practices in hydrodynamic modeling. The results should not be used for operational or decision-making purposes.

Intended use

The dataset is aimed at supporting educational, research, and exploratory activities, such as:

- Experimenting with coastal and ocean modeling using MIKE 21.
- Validating hydrodynamic model outputs with observational data.
- Developing methods for automatically calibrating model parameters.
- Building data-driven models, including machine learning surrogates of the MIKE simulation results.

Folder structure

The repository is organized in the following way

- README.md
- license
- model
 - MIKE model setup file (.m21fm)
 - log file (.log)
- input
 - meteorological forcing (wind, air pressure)
 - lateral boundary conditions (water level and currents)

- mesh file (.mesh)
- observations
 - csv files containing observational data for model validation
- code
 - Jupyter notebooks exploring the dataset
 - Jupyter notebooks for model validation using observations
 - a requirements file (.txt)
- figures
 - figures generated by notebooks
- output sample
 - a reduced MIKE model result data file (.dfsu and .dfs0)

Separately from the current repository, you can find the output zip file (in Zenodo):

- output
 - MIKE model result data (.dfsu and .dfs0)

Introduction


This folder contains data for a simulation with the MIKE 21 Flow Model FM of Conception Bay located in Newfoundland, Canada. The area is heavily influenced by semidiurnal tides from the Atlantic Ocean, and wind-driven circulation plays an important role too. The domain has one open boundary to the North.

This repository contains the setup file, input data and observation data, as well as simulation result data. The simulation result data is available in Zenodo. The data supplied in this repository covers the period from 2014-01-01 to 2022-12-31. There is a spin-up period, so it is recommended to remove the first 2 days of the result data.

The MIKE 21 Flow Model FM

MIKE 21 Flow Model FM is a modelling system based on a flexible mesh approach. The modelling system has been developed for applications within oceanographic, coastal and estuarine environments. The model is based on the numerical solution of the two-dimensional shallow water equations - the depth-integrated incompressible Reynolds averaged Navier-Stokes equations. More information can be found in the documentation.

The Conception Bay mesh consists of triangular elements in a higher resolution close to the coast than on deeper waters, and for each node a depth value is assigned by interpolating the bathymetry data. The mesh is shown in the figure below. It consists of a total of 8474 elements covering the area of approximately $900 \ km^2$.



A simulation can be performed with the MIKE modelling software, while supplying the following data for driving the model:

- the water levels and current velocities on the North boundary
- wind velocities and air pressure in the domain.

This input data can be found in the /input folder. Model parameters, e.g., bed resistance constant, can be calibrated by comparing the model simulations to observational data.

The outputs of the model are given as a timeseries for each mesh element on the spatial domain containing the variables: - the surface elevation, - the u and v components of the current velocity.

The output data can be found as a separate file in Zenodo. Once a simulation has been run, a log file will be generated. The log-file for the benchmark simulation is found in the folder /model, and it contains information on the parameters used and the time spent on the simulation.

Since all data, including output from a simulation, is given, it is not necessary to run the MIKE simulation. However, it is possible, since a setup file is supplied as well as all of the input data. Running the MIKE software requires a license. Read more about obtaining a license and about


academic licensing. If you already have a license, read the step-by-step guide to learn how to run simulations.

The input and output data are given as dfs files. These files can be processed using the MIKE IO Python package developed by DHI. Find more information on the data types in the MIKE IO documentation.


Model validation


The ModelSkill Python package developed at DHI can be used for validating the model outputs by comparing to observational data.

The model is validated by comparison to observational data from a measurement station in Conception Bay and altimetry data from satellites. This is done in the notebooks code/model_validation_*.ipynb. The leftmost figure below shows the location of the measurement stations, and the rightmost figure shows the coverage of the altimetry data.



Below, the comparison between the observational data from one such measurement station and MIKE 21 is shown first followed by the comparison to the altimetry data. The production of these and many more plots is found in the notebooks code/model validation *.ipynb.





Data sources

Several data sources contribute to this case. They are outlined below.

The following changes have been made to the data:

• Altimetry data: Data has been filtered to only include "good" data points according to quality flags.

Data	Source	Citation	License
Mesh	The mesh is	Repository citation,	CC BY 4.0
	developed by DHI.	see the top	

Data	Source	Citation	License
Bathymetry	Canadian Hydrographic Service	Fisheries and Oceans Canada, "Canadian Hydrographic Service Non-Navigational (NONNA) Bathymetric Data"	Open Government Licence - Canada, and the CHS NONNA Licence found in license.txt.
Wind and Air pressure	The ERA5 reanalysis of globate climate. Produced by Copernicus Climate Change Service at ECMWF.	(2024) Hersbach, H., Bell, B., Berrisford, P., Biavati, G., Horányi, A., Muñoz Sabater, J., Nicolas, J., Peubey, C., Radu, R., Rozum, I., Schepers, D., Simmons, A., Soci, C., Dee, D., Thépaut, J-N. (2023): ERA5 hourly data on pressure levels from 1940 to present. Copernicus Climate Change Service (C3S) Climate Data Store (CDS), DOI: 10.24381/cds.bd0915c (Accessed on 19-12-2023)	See full license here. Excerpt: "Access to Copernicus Products is given for any purpose in so far as it is lawful, whereas use may include, but is not limited to: reproduction; distribution; communication to the public; adaptation, modification and combination with other data and information; or any combination of the 6 foregoing."

Data	Source	Citation	License
Boundary condition	The surface elevation values for the boundary conditions are derived from the DHI regional North Atlantic HD storm surge model and combined with 42-years of tidal boundary conditions using the Bedford Institute of Oceanography (BIO) Government of Canada WebTide model, to create a total water level signal that includes both surge and tidal components. More information is found here.	The BIO model: Dupont, F., C.G. Hannah, D.A. Greenberg, J.Y. Cherniawsky and C.E. Naimie. 2002. Modelling System for Tides. Can. Tech. Rep. Hydrogr. Ocean Sci. 221: vii + 72pp. https://www.bio.gc. ca/science/research- recherche/ocean/ webtide/documents/ WebTide_report4. pdf.	BIO model disclaimer: "This program is distributed by the copyright holder and contributors in the hope that it will be useful. It is provided" AS IS" without warranties of any kind, whether express or implied. This includes, but is not limited to, merchantability or fitness for a particular purpose. In no event shall the copyright holder be liable for damages, including any general, special, incidental or consequential damages arising out of the use or inability to use the program (including, but not limited to, loss of use, data or profits). This program is not to be used for navigation purposes."

Data	Source	Citation	License
Sea levels in measurement stations	The data is from the Fisheries and Oceans Canada (DFO) historical water level gauge. No changes were made to the data. The data for the exact station can be found here.	DFO (2024). Marine Environmental Data Section Archive, https://meds-sdmm.dfo-mpo.gc.ca, Ecosystem and Oceans Science, Department of Fisheries and Oceans Canada. Data obtained on 2024/10/01.	The data is shared openly given it is cited as here. See more here.

Altimetry data

The altimetry data is extracted from a range of different sources. The data is based on satellite observations, and the data is downloaded using DHI's services for marine observation data. Data sources:

Satellite name	Owner	Link
CryoSat-2 (c2)	European Space Agency (ESA)	https://earth.esa.int/ eogateway/catalog/cryosat- products
SARAL (sa)	French National Space Agency (CNES) and Indian Space Research Organisation (ISRO)	https://podaac.jpl.nasa. gov/dataset/ALTIKA_ SARAL_L2_OST XOGDR
Jason-2 (j2)	National Aeronautics and Space Administration (NASA) and French National Space Agency (CNES)	https://podaac.jpl.nasa. gov/OSTM-JASON2
Sentinel-3B (3b)	European Space Agency (ESA)	https://sentiwiki. copernicus.eu/web/s3- altimetry-instruments