1. Get your release from the [Github repo](#)
2. Extract into the same folder that has the -Win64-Shipping.exe file
    a. For DRG, this is Deep Rock Galactic\FSD\Binaries\Win64
3. Launch the game, wait for the spacerig to load, and then inject the ue4ss.dll with whatever injector you use
    a. I use Cheat Engine, which you can get from [here](#) (be very careful when installing, as it will ask try to get you to install adware)
    b. To use CE, start the game and CE
    c. In CE, hit this little computer monitor button at the top under the File menu

d. Go to the processes tab and find DRG, select it, then hit open

e. Now hit the memory view button in the main UI
f. Then go to the tools menu and hit inject DLL

g. Then select ue4ss.dll
h. A confirmation box asking if you want to execute a function of the dll will come up, press no

4. Now you should see a console window open up with a bunch of info. The important part you need to make sure you can see is this "event loop start"

```
Setting up mods...
Starting mods...
Starting mod 'ObjectDumperMod'
Starting mod 'ConsoleEnablerMod'
Starting mod 'CheatManagerEnablerMod'
m_shared_functions: 0x7ffac2e62ed0
Event loop start
```

5. Now in-game, hit Alt + B and you should see this

```
Setting up mods...
Starting mods...
Starting mod 'ObjectDumperMod'
Starting mod 'ConsoleEnablerMod'
Starting mod 'CheatManagerEnablerMod'
m_shared_functions: 0x7ffac2e62ed0
Event loop start
[Lua] ConsoleClass: Class /Script/Engine.Console
[Lua] GameViewport: GameViewportClient /Engine/Transient.GameEngine_2147482596:GameViewportClient_2147482375
[Lua] Console constructed
[Lua] GameViewport.ViewportConsole: Console /Engine/Transient.GameEngine_2147482596:GameViewportClient_2147482375.Console_2147477976
[Lua] ConsoleKey[1]: F10
[Lua] ConsoleKey[2]: [Lua] ConsoleKey[3]:
```

6. This lists the console keys that it detects, although ConsoleKey[1] is always F10 by default.
So for DRG, the key above tab and left of 1 should work, but if not, F10 is fine

7. And there we go, console is back :)

```
>>> pog <<<
Command not recognized: pog

> _
```