



Configuring Apache Flink on EMR

This document contains the steps to setup Apache Flink on your EMR cluster along with the steps to open the Flink dashboard.

Note: Make sure that you have set up the EMR cluster(**version emr-5.31.0**) correctly with the Flink and Hadoop services installed and opened the port **8080** for your IP in order to access the Flink dashboard UI.

1. Login to your EMR cluster

```
Amazon Linux 2 AMI
https://aws.amazon.com/amazon-linux-2/
104 package(s) needed for security, out of 181 available
Run "sudo yum update" to apply all updates.
EEEEEEEEEEEEEEEEE MMMMMMM
                                    M:::::::M R:::::::::::::::::::R
E:::::::::::::::::E M::::::::M
EE:::::EEEEEEEEE:::E M:::::::M
                                  M:::::::M R:::::RRRRRR:::::R
             EEEEE M:::::::M
                                 M:::::::: M RR::::R
 E::::E
                  M::::::M:::M
                                M:::M:::::M
                                              R:::R
 E::::EEEEEEEEE
                  M:::::M M:::M M::::M M:::::M
                                              R:::RRRRRR::::R
 E::::::E
                  M:::::M M:::M:::M
                                              R::::::::RR
 E::::EEEEEEEEE
                            M:::::M
                                              R:::RRRRRR:::R
                  M:::::M
                                     M:::::M
 E::::E
                   M:::::M
                             M:::M
                                     M:::::M
                                              R:::R
                                                        R::::R
 E::::E
             EEEEE M:::::M
                             MMM
                                     M:::::M
                                              R:::R
                                                        R::::R
EE:::::EEEEEEEE::::E M:::::M
                                              R:::R
                                     M:::::M
M:::::M RR::::R
                                                        R::::R
EEEEEEEEEEEEEEEE MMMMMM
                                     MMMMMMM RRRRRRR
                                                        RRRRRR
[hadoop@ip-172-31-48-12 ~]$ |
```

2. Run the following command to make the following changes in the flink-conf.yaml file.

sudo vi /usr/lib/flink/conf/flink-conf.yaml





- 3. Now in this config file, you need to scroll down under the Common configuration where heap size for Job manager is set.
- 4. Here you need to uncomment the following two lines by removing the **hashtag** at the **start of those lines**. Press **i** to go into INPUT mode and uncomment these lines.

```
jobmanager.memory.process.size: 1600m
taskmanager.memory.process.size: 1728m
```





```
# The total process memory size for the JobManager.

# Note this accounts for all memory usage within the JobManager process

jobmanager.memory.process.size: 1600m

# The total process memory size for the TaskManager.

# Note this accounts for all memory usage within the TaskManager process

taskmanager.memory.process.size: 1728m

# To exclude JVM metaspace and overhead, please, use total Flink memory

# It is not recommended to set both 'taskmanager.memory.process.size' a

# taskmanager.memory.flink.size: 1280m
```

5. After this, you need to scroll down further to the Web Frontend section and then uncomment the **rest.port**, **rest.address**, **rest.bind-port** and **rest.bind-address** lines by removing the **hashtag** at the **start of those lines**. After you have pasted the lines, you can save by **pressing Escape and typing :wq** and finally pressing Enter.






6. Finally, you need to run the following command to start a flink yarn session. Please note that if you need to close the YARN session, you can type **stop** and press Enter.

flink-yarn-session

```
SiF43. See http://mem.st443.org/codes.html#multiple.bindings for an explanation.
SIF43. Extual hinding is of type Grg.apache.elink.configuration.GlobalConfiguration
3022-02-20 17:02:59,594 1NF0 org.apache.flink.configuration.GlobalConfiguration
3022-02-20 17:02:59,597 1NF0 org.apache.flink.configuration.GlobalConfiguration
3022-02-20 17:02:59,597 1NF0 org.apache.flink.configuration.GlobalConfiguration
3022-02-20 17:02:59,597 1NF0 org.apache.flink.configuration.GlobalConfiguration
3022-02-20 17:02:59,597 1NF0 org.apache.flink.configuration.GlobalConfiguration
3022-02-20 17:02:59,572 1NF0 org.apache.flink.configuration.GlobalConfiguration
3022-02-20 17:02:59,572 1NF0 org.apache.flink.configuration.GlobalConfiguration
3022-02-20 17:02:59,572 1NF0 org.apache.flink.configuration.GlobalConfiguration
3022-02-20 17:02:59,572 1NF0 org.apache.flink.configuration.GlobalConfiguration
3022-02-20 17:02:59,573 1NF0 org.apache.f
```

7. Now, you can open the Flink front-end by opening the following URL on your web browser. Make sure that you have opened port 8080 for your IP as mentioned in the EMR cluster configuration document. **Note**: The port might change to 8081 and if so, you will need to open that port for your IP.


<public DNS>:8080







8. To submit a new Flink job, you can navigate to the **Submit New Job** tab on the left.



9. To work with PyFlink, run the following command in a separate SSH session to the EMR cluster.

```
sudo yum update
sudo yum install python3-devel
sudo pip3 install apache-flink==1.11.0
```