

Practical no. 4

Name :- Danish Altaf Solkar

Enrolment no. :-24111590805

Class :- CO3K – B

Subject :- OOP

Aim :- To define a class Student having data members name and roll no.
Accept and display data for one object.

Program :-

```
#include<iostream.h>

#include<conio.h>

class Student
{
public:
int roll_no;
char name[30];
void accept()
{
cout<<"\nEnter your name:- ";
cin>>name;
cout<<"\nEnter your roll no. :- ";
cin>>roll_no;
}
void display()
{
cout<<"\nYour name:- "<<name;
cout<<"\nYour roll no. :- "<<roll_no;
}
};
```

```
void main()
{
Student s1,s2;

clrscr();

s1.accept();


s1.display();

s2.accept();

s2.display();

getch();
}
```

OUTPUT:-

A screenshot of a DOSBox 0.74 terminal window. The title bar at the top reads "DOSBox 0.74, Cpu speed: max 100% cycles, Frameskip". The terminal has a black background with white text. It shows the execution of a program that prompts for student names and roll numbers. The input "Danish" and "60" is entered for the first student, and "Ayaan" and "55" for the second. The program then displays the entered information for each student.

```
DOSBox 0.74, Cpu speed: max 100% cycles, Frameskip
Enter your name:- Danish
Enter your roll no. :- 60
Your name:- Danish
Your roll no. :- 60
Enter your name:- Ayaan
Enter your roll no. :- 55
Your name:- Ayaan
Your roll no. :- 55
```

**Aim :- To define a class Room with data members length, breadth and height.
Member function area() and volume().**

Program :-

```
#include<iostream.h>

#include<conio.h>

class Room

{

public:

float l,b,h;

void area()

{

float area=l*b;

cout<<"\nArea of room:- "<<area;

}

void volume()

{

float vol=l*b*h;


cout<<"\nVolume of room:- "<<vol;

}

};
```

```
void main()
{
    Room r1;
    r1.l=7.456;
    r1.b=8.345;
    r1.h=9.876;
    clrscr();
    r1.area();
    r1.volume();
    getch();
}
```

OUTPUT:-

A screenshot of a DOSBox 0.74 window. The title bar reads "DOSBox 0.74, Cpu speed: max 100% cycles, Frameskip". The main window area is black with white text. The text displayed is "Area of room:- 62.220322" on the first line and "Volume of room:- 614.487915" on the second line.

```
DOSBox 0.74, Cpu speed: max 100% cycles, Frameskip
Area of room:- 62.220322
Volume of room:- 614.487915
```