
Topology Diagram



Addressing Table

Device	Interface	IP Address	Subnet Mask	Default Gateway
R1	Fa0/0			N/A
	S0/0/0			N/A
R2	Fa0/0			N/A
	S0/0/0			N/A
PC1	NIC			
PC2	NIC			

Learning Objectives

Upon completion of this lab, you will be able to:

- Subnet an address space given requirements.
- Assign appropriate addresses to interfaces and document.
- Configure and activate Serial and FastEthernet interfaces.
- Test and verify configurations.
- Reflect upon and document the network implementation.

Scenario

In this lab activity, you will design and apply an IP addressing scheme for the topology shown in the Topology Diagram. You will be given one address block that you must subnet to provide a logical addressing scheme for the network. The routers will then be ready for interface address configuration according to your IP addressing scheme. When the configuration is complete, verify that the network is working properly.

Task 1: Subnet the Address Space.

Step 1: Examine the network requirements.

You have been given the 192.168.1.0/24 address space to use in your network design. The network consists of the following segments:

- The network connected to router R1 will require enough IP addresses to support 15 hosts.
- The network connected to router R2 will require enough IP addresses to support 30 hosts.
- The link between router R1 and router R2 will require IP addresses at each end of the link.

-	: Consider the following questions when creating your network design.
How m	any subnets are needed for this network?
What is	s the subnet mask for this network in dotted decimal format?
What is	s the subnet mask for the network in slash format?
How m	any usable hosts are there per subnet?
Step 3	: Assign subnetwork addresses to the Topology Diagram.
1.	Assign subnet 1 to the network attached to R1.
2.	Assign subnet 2 to the link between R1 and R2.
3.	Assign subnet 3 to the network attached to R2.
Task 2:	Determine Interface Addresses.
Step 1	: Assign appropriate addresses to the device interfaces.
1.	Assign the first valid host address in subnet 1 to the LAN interface on R1.
2.	Assign the last valid host address in subnet 1 to PC1.
3.	Assign the first valid host address in subnet 2 to the WAN interface on R1.
4.	Assign the last valid host address in subnet 2 to the WAN interface on R2.
5.	Assign the first valid host address in subnet 3 to the LAN interface of R2.
6.	Assign the last valid host address in subnet 3 to PC2.
Step 2	: Document the addresses to be used in the table provide under the Topology Diagram.
Task 3:	Configure the Serial and FastEthernet Addresses.
Step 1	: Configure the router interfaces.
Please	ure the interfaces on the R1 and R2 routers with the IP addresses from your network design. note, to complete the activity in Packet Tracer you will be using the Config Tab. When you have d, be sure to save the running configuration to the NVRAM of the router.
Step 2	: Configure the PC interfaces.
	ure the Ethernet interfaces of PC1 and PC2 with the IP addresses and default gateways from your k design.
Task 4:	Verify the Configurations.
Answe	r the following questions to verify that the network is operating as expected.
From tl	he host attached to R1, is it possible to ping the default gateway?
From th	he host attached to R2, is it possible to ping the default gateway?
From th	he router R1, is it possible to ping the Serial 0/0/0 interface of R2?
From tl	he router R2, is it possible to ping the Serial 0/0/0 interface of R1?
	swer to the above questions should be yes . If any of the above pings failed, check your physical ctions and configurations.

Task 5: Reflection
Are there any devices on the network that cannot ping each other?
What is missing from the network that is preventing communication between these devices?