

API Base Domain: <https://dev-crms.unimoniindia.com>

Step 1: Authentication – JWT Bearer Token Generation

API URL: <https://dev-crms.unimoniindia.com/CrmDataWS/api/v2/uni-secure/oauth2/token>

Method: **POST**

Content Type: **application/x-www-form-urlencoded**

Request Parameters (Body):

PARAMETER	VALUE(SAMPLE/PLACEHOLDER)
client_id	ecogo
client_secret	NQBONKNSwgAC0BcIhB0ytEhEORh3GGXhrqWIJtMmey8
grant_type	client_credentials

Sample Response:

```
{
  "issuer"      : "unimoni-auth-server",
  "token_type"  : "Bearer",
  "status"     : "active",
  "role"       : "ECOGO",
  "oauth_tokens" : {
    "access_token" : "GENERATED ACCESS TOKEN",
    "expiry"       : "1-hour"
  }
}
```

IMPORTANT:

Single-use Token: Each token is valid for only one request. For every new API request, a new token must be generated.

Step 2 : Customer Registraton API

API URL: <https://dev-crms.unimoniindia.com/CrmDataWS/api/v2/pctCustRegister>

Method: **POST**

Authorization Header: **Authorization: Bearer <access_token>** (use the token from Step 1)

Request Body:

```
{
  "cust_name": "",
  "cust_mobile": "", //10 digit mobile number
}
```

```
"cust_email": "", //NA if not available
"cust_dob": "", //Jan 1 1900 if not available
"referredby_crmcode": "0",
"referredby_mobile": "0",
"product_code": "0003",
"sub_product_code": "NA",
"cust_source": "S188",
"remarks": "Ecogo Entry",
"add_branch": "KL94",
"add_user": "ECOGO"
}
```

Successful Response:

```
{
  "respcode": "200",
  "respdesc": "Success",
  "status": "Success",
  "sourceDomain": "unimoni",
  "data": {
    "cust_code": "XXXXX",
    "is_already_registered": ""
  }
}
```

Failure Responses:

```
{
  "respcode": "400",
  "respdesc": "",
  "status": "Failure",
  "sourceDomain": "unimoni",
  "data": {
    "cust_code": ""
  }
}
```