Samsung TV Remote Commands							
Command	Interface	Push #	Command	Interface	Push #		
on	WOL		arrowRight	WS	9		
off	WS		arrowUp	WS	10		
mute	WS	2	arrowDown	WS	11		
unmute	WS	2	enter	WS	12		
volumeUp	WS	21	numericKeyPad	WS	3		
volumeDown	WS	22	home	WS	14		
play	WS		menu	WS	23		
pause	WS		guide	WS	20		
stop	WS		sourceSetOSD	WS			
exit	WS	13	sourceToggle	WS	35		
return	WS	4	channelList	WS	26		
fastBack	WS	36	channelUp	WS	18		
fastForward	WS	37	channelDown	WS	19		
arrowLeft	WS	8	previousChannel	WS	34		
(App Commands : all start with "app")							
appOpenByName	LAN		Requires setup of a	ppData us	sing		
appClose	LAN		preferences.				
Art Mode Commands							
Command	Interface	Push #	Descr	iption			
art Mode	WS	6	Toggles ArtMode for Frame TV				
ambientMode	WS	7	Turns on AmbientMode for non-Frame TV				
SmartThings Commands							
setVolume	ST		set volume				
setLevel	ST		set volume				
setPictureMode	ST		sets pictureMode. state.pictureModes				
togglePictureMode	ST	43	toggles through the		des		
			using state.pictureN	•			
setSoundMode	ST		sets soundMode. S				
			state.soundModes.				
	0.7	42	toggles through the	soundMod	des		
toggleSoundMode	ST		using state.soundM				
	ОТ		sets inputSource.				
sourceSetSt	ST		state.supportedInpu	uts			
	Other Commands						
channelSet	Hybrid		Input channel. If S	T, sets cha	nnel via		
			STs. If not, sets via	a entry of c	ligits the		
			return through WS	interface.			
sendKey	WS		Requires entry of key text.				
presetCreate	TV		Select presetNo (1	- 10). Crea	ntes		
			preset representing nowPlaying.	the attribu	ıt		

presetExecute	TV	51 - 60 Select presetNo (1 - 10). Attempts to run selected preset.		
presetCreateTv	TV	Allows creating a TV channel preset if ST is not running. Requires entry of data.		
presetUpdateNext	TV	For use in dashboards. When pressed, changes the presetExecut command to presetCreate.		
Button 44 - open app	TV	44	Requires variable to be set (capability variable). Passes data to appOpenBy name.	
Button 45 - tv channel preset create	TV	45	Requires variable to be set (capability variable). Passses data to preset create tv using format psNo, channel, channelTitle.	
Button 46 - channel set		46	Requires variable to be set (capability variable). Passses data to channelSet.	