


CONVERSATION MODE

In this mode, the user speaks via microphone and the ai agent replies. The user can interrupt the agent by speaking on top of his response.



During the conversation, the user can change the agent, or start a new conversation.

KEYBOARD


PTT MODE		
SPACE	(push to talk)	records audio until space is released
ESCAPE	(press once)	stops current response
ESCAPE	(press twice)	restart the session with no history
U		undo last response/message
CONTROL + S		configure agents (or select one)
CONTROL + E		save session (audio/text/html) (or stop saving)
ARROW LEFT/RIGHT		swap to previous / next agent in settings file
ARROW UP/DOWN		increase / decrease voice speed in next agent turn
CONTROL + D		switches to debate mode
CONTROL + C		exits program

LIVE MODE

SPACE	(press once)	pause/resume user recording
ESCAPE	(press once)	stops current response
ESCAPE	(press twice)	restart the session with no history
U		undo last response/message
CONTROL + S		configure agents (or select one)
CONTROL + E		save session (audio/text/html) (or stop saving)
ARROW LEFT/RIGHT		swap to previous / next agent in settings file
ARROW UP/DOWN		increase / decrease voice speed in next agent turn
CONTROL + D		switches to debate mode
CONTROL + C		exits program

DEBATE MODE

In this mode, the user gives a subject and 2 agents initialize a debate. The user can participate too.



The debate runs indefinitely until stopped, or until max turns is reached (if configured).

KEYBOARD


PTT MODE		
SPACE	(push to talk)	records audio until space is released
ESCAPE	(press once)	pause debate until next user input
ESCAPE	(press twice)	restarts the debate with no history
U		undo last response/message
CONTROL + S		configure agents (or select one)
CONTROL + E		save session (audio/text/html) (or stop saving)
ARROW UP/DOWN		increase / decrease voice speed in next agent turn
CONTROL + D		switches to conversation mode
CONTROL + C		exits program

LIVE MODE

SPACE	(press once)	pause/resume user recording
ESCAPE	(press once)	pause debate until next user input
ESCAPE	(press twice)	restarts the debate with no history
U		undo last response/message
CONTROL + S		configure agents (or select one)
CONTROL + E		save session (audio/text/html) (or stop saving)
ARROW UP/DOWN		increase / decrease voice speed in next agent turn
CONTROL + D		switches to conversation mode
CONTROL + C		exits program

READ MODE

This mode reads a text file with voice (tts) or an input text, phrase by phrase, highlighting the current phrase. The user can navigate and pause/resume. Use -r cli option to start this mode.



KEYBOARD

SPACE	pause/resume reading
ARROW UP	move to the previous phrase
ARROW DOWN	move to the next phrase
CONTROL + C	exits program

BACKGROUND MODE

When vtmate runs in background mode (also called daemon mode) you can use the next functionality from anywhere in your computer. No need to be focused in the terminal. To start the background mode use vtmate --daemon.

KEYBOARD

CTRL + ALT + A	push to talk (selecting text adds context)
CTRL + ALT + R	select text, then read it aloud
CTRL + ALT + S	push to talk, paste speech as text
CONTROL + Q	(press once) stops current speech
CONTROL + Q	(press twice) resets the conversation

SETTINGS FILES

~/vtmate/agents	agents definition file (llm, language, voice, system prompt...)
~/vtmate/settings	global shortcuts customization file used in background mode

CLI OPTIONS

-a <agent_name>	set a specific initial agent
-p <prompt>	initialize with a text prompt
-i <file.txt>	initialize with a file prompt
-i -	initialize with prompt from STDIN
-q	produce a single response and exit (requires -p or -i options)
-s	save the conversation to text and audio file in ~/vtmate/conversations or ~/vtmate/read-files
-s-html	save conversation as html player + audio per turn

--debate <AGENT1> <AGENT2> [SUBJECT]	start debate from text
--debate <AGENT1> <AGENT2> -i <FILE>	start debate from text file
--debate <AGENT1> <AGENT2> -i -	start debate from stdin text
--max-turns <N>	end the program after N debate turns

-r <file.txt>	read a file with voice, phrase by phrase (no llm)
-r -	read text from STDIN with voice, phrase by phrase
-r-stdout <file.txt>	no screen/nav: speech to STDOUT as wav (no llm)
-r-stdout -	same, but reads the text to speak from STDIN
--stt <WAV_FILE>	speech to text from a wav file (no llm, no tts)
--stt -	speech to text from STDIN wav (no llm, no tts)
-c <agents_file>	use a specific agents file instead of ~/vtmate/agents
--list-voices	list all voices for all languages and tts systems
--render-quicksheet-pdf	save this printable quicksheet as PDF
--ptt <true/false>	override for this session the ptt setting for all agents independently of its settings

--daemon	start vtmate in the background (global hotkeys, voice only)
--daemon-stop	stop the running daemon
--daemon-status	show whether a daemon is running and its hotkeys

--clone-voice <NAME> <LANG> <WAV> <REF_TEXT>	train new voice from .wav
--refine-voice <NAME> <LANG> <WAV> <REF_TEXT>	refine an existing voice

--version	print version
-----------	---------------

--nb	do not render the vtmate banner
--verbose	run the program in verbose mode
--help	show help

COMMAND EXAMPLES

```
vtmate
vtmate -s
vtmate -p "explain me the Pomodoro technique?"
vtmate -a "planner" -p "How to learn math quickly?" -q
vtmate -p "Give me SEO keyword ideas for tts systems" -q -s
```

```
vtmate -i prompt.txt
vtmate -i prompt.txt -q
vtmate -i prompt.txt -q -s
echo "What are those files? \n $(find ~ | grep -100)" | vtmate -i -
echo "Summarize this: \n\n $(cat article.txt)" | vtmate -i - -q
echo "What to improve: \n\n $(cat article.txt)" | vtmate -i - -q -s
```

```
vtmate --debate Aristoteles Budda "How to find ever lasting peace?"
vtmate --debate Budda Aristoteles "Teach me about logic" -s-html
vtmate --debate Aristoteles Budda -i article.txt --max-turns 10 -s-html
echo "Thoughts? $(cat article.txt)" | vtmate --debate Budda Hegel -i -
```

```
vtmate -r article.txt
vtmate -a Budda -r article.txt -s
echo "One phrase. Second phrase" | vtmate -r - -s
vtmate --stt recording.wav
```

PTT / LIVE MODES EXPLAINED

LIVE mode is a hands free functionality, which continuously records and only submits the audio on a certain audio level threshold and after a certain silence time; it requires configuring audio level threshold and end silence to detect your voice (depends on ambient noise and mic levels). To set it up set your agent settings to ptt=off and adjust sound_threshold_peak and end_silence_ms fields. LIVE mode is the default mode and to talk you have to keep SPACE pressed and then release. Keep PTT mode for all agents if you struggle with configuration (ptt=on)