The today's laboratory task is to implement a python script called **cryptocat** which simulates the linux command **netcat** or **nc** (which can read/write data using tcp/ip connections, see below) extended with the functionalities necessary to encrypt/decrypt transmitted data. This can be done using the **openssl enc** command.

With the command netcatyou can connect to a remote host(or locally on localhost) and connect to *stdin* and *stdout* stream data sent or received from remote. In particular, the command netcat or nc can be used:

## - in server mode with the syntax:

```
netcat -l port or netcat -l -p port
```

-1 is the option to activate *listen* mode that puts server in "listening" state on a given TCP port. port is an integer that specifies the *port number* on which the server is listening

## - in client mode with the syntax:

```
netcat <hostname> port
```

hostname is the IP address of the server to connect to;

port is an integer that specifies the port number to be connected to.

In "listen" mode netcat listens on a port until some remote client connects to it (clients may also be local). At this point it will be established a link between the client and server. In client mode, instead, netcat connects to a remote server and can send data.

The easier and primary netcat use is that of a very simple **server-client** data transfer.

For example, one can create on pc1 (which has IP address 192.168.0.1) a server listening on port 3333 by typing the command:

```
netcat -1 3333
```

## On pc2 instead one executes the command:

```
netcat 192.168.0.1 3333
```

with which you connect by using netcat to pc1 on port 3333.

At this point everything you write in pc1's console will be transferred to pc2 and vice versa, because the standard input of a pc is connected to the standard output of the other. Transferring a file is as easy as

```
netcat -1 3333 > destinationfile
netcat 192.168.0.1 3333 < sourcefile</pre>
```

Respectively on the server and client machines.

Using the command openssl enc one can encrypt and decrypt data blocks with a large set of cryptographic algorithms. Specifically, the command openssl enc can be used with the sintax:

```
openssl enc [-algorithm] [-e] [-d] [-k key] [-in file] [-out file]
```

- algorithmis used to indicate the algorithm used to perform the symmetric encryption operation (the full list of available algorithms displays with openssl enc -h)
- -e operation to be done is *encryption* (excludes the -doption)
- -d operation to be done is decryption (excludes the -e option)
- -k key for symmetric encryption operation
- -in file the input file to encrypt (takes stdin if not specified)
- -out file the output file encrypted (takes stdout if not specified)
- -base64 to have the output in base64 (useful if preparing data to be sent as text)

## The **cryptocat** script should be invoked as follows:

```
cryptocat [options][hostname] port
```

- options is a parameter that includes a list of options as:
  - o −1, if present, will activate listen mode, that is, server mode
  - o -k *key* for setting a key for encryption operation
  - $\circ$  -a algorithm, if present, can be used to indicate the algorithm used to perform the encryption/decryption operation otherwise we assume a default algorithm;
- hostname an optional parameter that indicates when cryptocat is invoked in client mode the IP address of the server to connect to
- port is an integer that specifies the port number to which to connect as client or listen as

server If executed in client mode (without the option -1), the script:

- 1. reads from *stdin* and encrypts data stream that has been read using the command opensslenc (which will be invoked with parameters specified, for example, key, algorithm)
- 2. sends the encrypted data stream (in base64) to server hostname on port port Using the netcat command

If executed in server mode (with the option -1), the script:

- 1. invokes the netcat command in *listen* mode, then listens on port port until it doesn't receive data stream from a client.
- 2. reads data stream from client and writes it decrypted on *stdout* using opensslenc command (which will be invoked with parameters specified, for example, key, algorithm).

Tip: recall that it is possible to pipe the linux commands *cat*, openssl *enc* and *netcat for* (1) providing a data stream, (2) encrypting, and (3) sending to the remote server; on the server side it is possible to pipe the commands netcat and openssl enc for (1) listening for a data stream from client, and (2) decrypting it.

Run the script **cryptocat** in both modes (two different shell) analyzing the data traffic between server and client with the **Wireshark** software.