

Quick Tech Hacks

Powered by
Learning Technology



Your go-to guide for technology troubleshooting



Joining Issues 🖱️

Troubleshoot Joining issues



Audio Issues 🖱️

Troubleshoot Audio concerns



Unable to See/View Presentation 🖱️

Troubleshoot Presentation issues



Camera issues 🖱️

Troubleshoot Camera issues



Screen sharing issues 🖱️

Troubleshoot Screen sharing issues



If the issue needs to be escalated to CIO/Microsoft 🖱️

Steps to collect logs

Note: If the tech hacks steps do not resolve issues or if you need immediate assistance, please ping/email us @VILTTechSupport@accenture.com

1

Verify the Meeting Link

- Double-check the meeting invite link for errors.
- Copy and paste the link into a browser if it doesn't work directly in the Teams app.

- If the Teams app isn't working, try joining via the web client at Microsoft Teams Web.
- Use an updated browser like Chrome or Edge.

2

Try to Join Through the Browser

3

Check Internet Connectivity

- Ensure your internet connection is stable and fast enough to support a Teams meeting.
- Restart your router or switch to a different network if needed.

- Go to **Help** → **Check for Updates** to ensure Teams is up to date.

4

Check for Teams Updates

5

Clear Teams Cache

- **Windows:** Close Teams, go to run command and copy **%appdata%\Microsoft\Teams\Cache**, and delete the contents.
- **Mac:** Go to ~/Library/Application Support/Microsoft/Teams and remove cache files.
- Restart Teams.

In case the above steps do not resolve issues or if you need any immediate assistance, please ping/email us @vILTTechSupport@accenture.com



1

Exit and Rejoin

- Exiting and rejoining will fix most of the issues .

- Click your **Profile Icon** (top-right).
- Go to **Settings** → **Devices**.
- Select the correct microphone and speaker/headset.

2

Verify Audio Settings in Teams

3

Check System Sound Settings

- Right-click the sound icon in the taskbar and open **Sound Settings**.
- Select the correct playback and recording devices.
- Test sound using another app (e.g, media player).

- Most of the time quitting and restarting Teams can fix audio issues.
- To Quit the **Teams** – **Right-click** on the MS Teams icon – Click on Quit – Re-join the session.

4

Restart Teams

5

Check for Teams Updates

- Go to **Help** → **Check for Updates** to ensure Teams is up to date.

- Poor network connectivity can impact audio quality. Check your internet connection and consider using a stable connection for better stability.

6

Restart Teams

In case the above steps do not resolve issues or if you need any immediate assistance, please ping/email us @vILTTechSupport@accenture.com



Unable to See/View Presentation

[Home](#)

1

Exit and Rejoin

- Exiting and rejoining will fix most of the issues

- Applications using your display or screen recording (e.g., Other websites or tools/software) can conflict. Close all unnecessary apps before sharing.

2

Close Other Applications

3

Check Network Stability

- Ensure a stable internet connection, as poor connectivity can interfere with screen sharing.

- Go to **Settings** → **About** → **Check** for updates to ensure Teams is up to date.

4

Update Microsoft Teams

5

Restart Teams

- Quitting and restarting Teams can fix presentation issues.
- To Quit the **Teams** – **Right-click** on the MS Teams icon – Click on Quit – Re-join the session.

In case the above steps do not resolve issues or if you need any immediate assistance, please ping/email us @vILTTechSupport@accenture.com



1

Ensure the Webcam Slider is Open

- If your webcam shows a black screen, the shutter might be closed. Always open the shutter before turning on the webcam.
- In Teams, go to **Settings** → **Devices** and ensure the correct camera is selected under "Camera."

- Click your profile picture → **Settings** → **Devices**.
- Select your webcam under **Camera**.
- Test video quality in **Device Settings**.

2

Adjust Video Settings in Teams

3

Close Unwanted Background Applications

- Close apps that might use the webcam or consume bandwidth (e.g., other video conferencing tools, streaming platforms).

- Windows: Go to Settings → Privacy → Camera, and toggle Teams access to "On."
- Mac: Go to System Preferences → Security & Privacy → Camera and allow access.
- If issues persist, it might be due to policy restrictions. Consult the CIO team or raise an incident for assistance.

4

Check Permissions

5

Verify Background Settings

- Before joining a meeting, click on the "Background filters" option.
- Test the webcam without a background to see if the issue persists.

In case the above steps do not resolve issues contact CIO
[Create an Incident](#)



1

Exit and Rejoin

- Exiting and rejoining will fix most of the issues

- Only presenters can share screens. If you're an attendee, ask the organizer to change your role:
- Click **Participants** → right-click your name → select **Make a Presenter**.

2

Verify Your Role in the Meeting

3

Network Stability

- Slow or unstable network will affect screen sharing, try switching to a stable connection or move closer to the router

- Quitting and restarting Teams can fix presentation issues.
- To Quit the **Teams** – **Right-click** on the MS Teams icon – Click on Quit – Re-join the session.

4

Restart Teams

In case the above steps do not resolve issues or if you need any immediate assistance, please ping/email us @vILTTechSupport@accenture.com



Steps to collect the logs






Home

Collect these logs for Windows in either of the below two ways

1

Step

- Click on the up-arrow key from the taskbar to see all the applications, look for MS Teams.
- Right-click on the MS Teams application icon and select Collect Support Files.
- Once you click on the collect support files it will automatically get saved in the user's downloads folder.



2

Step

- By pressing Ctrl+Alt+Shift+1, these 4 keys together on the keyboard.

(Ref article: [Configure log files for monitoring and troubleshooting in Teams - Microsoft Teams | Microsoft Learn](#))

Note: Please move both folders (PRsOD-WebLogs and MSTEams Support Log) from your Downloads folder into the chat window. Alternatively, you can upload them to OneDrive and share the link through chat or email, making sure that Tech Support/LEP has the necessary access.