

## Copyright Information

This document is the exclusive property of International Air Transport Association (IATA). The recipient agrees that they may not copy, transmit, use or disclose the confidential and proprietary information in this document by any means without the expressed and written consent of IATA. By accepting a copy, the recipient agrees to adhere to these conditions to the confidentiality of IATA's practices and procedures; and to use these documents solely for responding to IATA's operations methodology.

IATA © 2005, All rights reserved

## **Revision History**

Ver.	Change Description	Sections	Date	Author(s)	Reviewer(s)	Approval(s)
1.0	Document Created		2006-05-09			

#### **Trademarks**

All other company and product names used herein may be the trademarks or registered trademarks of their respective companies.

# **Table Of Contents**

Copyright Information	2
Revision History	2
Trademarks	
1. Installation procedure	
1.1. Root and Issuing CA Certificate download	
1.2. Instructions for Acrobat Reader 6.0	4
1.3. Instructions for Acrobat Reader 7.0	4
List Of Figures	
Figure 1: Correct configuration for Acrobat Reader 6.0	

## 1. Installation procedure

Each of the electronic invoices issued by IATA is electronically signed in compliance with the national provision in the law of the EU Directive 2001/115/EC. In order to verify the signature of the invoices, you will need to perform the steps described in Section 1.1. Then, depending on the version of Acrobat Reader you are using, follow instructions in Sections 1.2 or 1.3.

### 1.1. Root and Issuing CA Certificate download

Download and import the two certificates in Internet Explorer. Please follow the steps below to install each of the root and issuing certificate CA certificates listed above:

- Click on the link of the root/issuing CA certificate to be installed.
- Click the open button in the dialog box.
- In the Digital Certificate dialog box, click on Details to view the information of the root/issuing CA certificate.
- Click on install Certificate to install the root/issuing CA certificate.
- In the **Certificate Manager Import Wizard** dialog box, click on **Next** and select "Automatically select the certificate store based on the type of certificate" option.
- Click Next and then Finish.
- Follow instructions in Section 1.2 if you are using Acrobat Reader 6.0.
- Follow instructions in Section 1.3 if you are using Acrobat Reader 7.0.

#### 1.2. Instructions for Acrobat Reader 6.0

- In the Preference dialog box, select Digital Signatures on the left, and then click on Advanced Preferences.
- In the Microsoft Windows Certificates Security box, do the following:
  - Specify that you want to import and use identities from the Windows Certificate Store
  - Specify that you want to trust all root certificates for both 1) validating signatures and
    validating certified documents.

#### 1.3. Instructions for Acrobat Reader 7.0

- In the Preference dialog box, select Security on the left, and then click on Advanced Preferences
- Click the Windows Integration tab, and do the following:
  - Specify that you want to import and use identities from the Windows Certificate Store
  - Specify that you want to trust all root certificates for both 1) validating signatures and 2) validating certified documents.




Figure 1: Correct configuration for Acrobat Reader 6.0.




Figure 2: Correct configuration for Acrobat Reader 7.0.