User Flow

How each user works through the system, by role. The order of the work is in Flow Chart; the pages are in Site Map.

Roles

Role	Department	Who	First page
Admin	any (only a label)	Owner / office: does everything	Dashboard: order tiles, invoice tiles, chart
Worker	Sales	Sale Worker: quotations (a production order is only read)	Dashboard: order tiles
Worker	Factory	Factory Worker: the processes, production, stock, purchase	Dashboard: order tiles

A Worker must have the department `Sales` or `Factory`; the department decides what the Worker can do. There is no sign-up and no forgot-password: an Admin makes the accounts and sets the passwords.

Everyone: sign in and move around




Figure 1. Everyone: sign in and move around

- The menu hides what the user may not use; the backend checks the same rules on every call.
- A menu that has only one visible entry is shown as that entry alone.
- An unknown address opens the Not found page; old addresses of moved pages are redirected.

Sale Worker

Pages




Figure 2. Pages

Make and confirm a QT




Figure 3. Make and confirm a QT

After Confirm




Figure 4. After Confirm

What the Sale Worker cannot do: add or change the processes of an order, start production, record progress, change stock, open Purchase, Accounting, Suppliers or Users. A confirmed QT is locked and cannot be deleted; an order cannot be made by hand, only by Confirm QT.

Factory Worker

Prepare and start an order




Figure 5. Prepare and start an order

Record progress




Figure 6. Record progress

Purchase and stock




Figure 7. Purchase and stock

A Factory Worker cannot reopen a Completed process (Admin only), cannot change QT, customers, products or materials, and cannot open Accounting or Users.

Purchase (Factory Worker and Admin)




Figure 8. Purchase (Factory Worker and Admin)

Suppliers and their items and prices are kept by the Admin; the Factory Worker can only view them.

Admin




Figure 9. Admin

The Admin can do everything the two Workers can.

Admin: accounting




Figure 10. Admin: accounting

Master data




Figure 11. Master data

Sale Worker: view customers and products. Factory Worker: view products and suppliers.

Who can do what

Area	Admin	Sale Worker	Factory Worker
Dashboard	all tiles + chart	order tiles	order tiles
QT: create, print, upload PO, confirm, delete a Draft	yes	yes	no access
Production orders: view	yes	yes	yes
Production orders: add / edit the processes before start	yes	no	yes
Start production, record progress	yes	no	yes
Reopen a Completed process	yes	no	no
Evidence upload (production order)	yes	no	yes
Stock: view and movements	yes	yes	yes
Stock changes by hand	yes	no	yes
Materials: add, edit, delete	yes	no	no
Purchase: PO, status, print, payment, files	yes	no	yes
Suppliers	yes	no	view only
Customers	yes	view only	no
Products	yes	view only	view only
Invoices, receipts	yes	no	no
Users	yes	no	no

Print and upload (any page with files)




Figure 12. Print and upload (any page with files)

Page	Files
QT	customer PO
Production order	evidence: images and documents (Admin, Factory)
Purchase order	PO file, quotation, other files

Errors a user may see

Message	When	What to do
Invalid credentials	wrong email or password	try again; ask the Admin to reset
403 Forbidden page	a page or action the role may not use	go back; ask the Admin
409 STOCK_SHORT	start production without enough material	purchase or add stock, then start again
Validation error	a required field is missing (QT without customer or line)	fill the field
In use	delete of a record other records use	keep it, or remove the uses first
Session ended	token expired or password changed	sign in again