ITEC 235-940 System Administration


Microsoft DNS Lab

Introduction


The Microsoft Domain Name System (DNS) server role translates a fully qualified domain name to an IP address. DNS is automatically installed whenever Active Directory is added to Microsoft Server. This lab provides a brief overview of Microsoft DNS Server.

1. Start and log onto Microsoft Server 20xx.


2. Click **Start**, **Windows Administrative Tools**, and then select **DNS**.




3. Click on the icon in the left column representing your server.




4. Double click the **Forward Lookup Zones** folder and then double click the **_msdcs.xxxx.local** zone. The _msdcs.xxxx.local (Microsoft Domain Controller Service) zone was created automatically when the server was promoted to a domain controller. This zone provides DNS records for services such as the Global Catalog, Kerberos, and Lightweight Directory Access Protocol. You should refrain from modifying the records in this zone.




5. Right click on the **xxx.local** Forward Lookup Zone and click on **New Host (A or AAAA)**.




6. Enter *data* in the **Name** field and the IP address of your domain controller in the **IP address:** field. Click the **Add Host** button. Click the **OK** button.




7. Open a command prompt, type **ping data**, and press the **Enter** key. Notice that the IP address of your server is returned. Create a screen capture of the completed ping command for your lab submission. Leave the command prompt open.



My Answer:



8. Right click on **Revere Lookup Zones** and then select **New Zone**.




9. Click the **Next** button on the New Zone Wizard.

10. Click the **Primary zone** radio button and then click on the **Next** button.

11. Select the **To all DNS servers running on domain controllers in this domain: itec.local** radio button. Click the **Next** button.

12. Select the **IPv4 Reverse Lookup Zone** radio button.


13. Select the **Network ID:** radio button. Enter the first three octets of your server's IP address in the field provided. Click the **Next** button.




14. Select the **Allow only secure dynamic updates** radio button. Click on the **Next** button.

15. Click the **Finish** button.


16. Rick click on the Reverse Lookup Zone you just created and click on **New Pointer (PTR)**.




17. Enter the IP address of your server in the **Host IP Address:** field.




18. Click the **Browse** button. Double click the Server and Forward Lookup Zone folder icons. Select the Forward Lookup Zone. Click the **OK** button to close the Browse window and then click the OK button to close the New Resource Record window.




19. Click on your server and click on the **OK** button.



20. Return to the command window. Enter the command **nslookup** followed by the IP address of your server to perform a reverse DNS lookup. See the screen capture below for an example. Create a screen capture of the completed nslookup command for your lab submission.



My Answer:


Windows Server 2022 - VMware Workstation
File Edit View VM Tabs Help
Library
Type here to search
My Computer
Windows Server 2022
Windows 10 x64
Home
Windows Server 2022
Windows 10 x64
Recycle Bin
Command Prompt
Microsoft Windows [Version 10.0.20348.1850]
(c) Microsoft Corporation. All rights reserved.
C:\Users\Devin Roach>nslookup 192.168.44.5
Server: UnKnown
Address: ::1
Name: itec235srv.itec.local
Address: 192.168.44.5
C:\Users\Devin Roach>
ODBC Data Sources (64-bit) 5/8/2021 3:14 AM Shortcut 2 KB
Performance Monitor 5/8/2021 3:14 AM Shortcut 2 KB
Recovery Drive 5/8/2021 3:14 AM Shortcut 2 KB
31 items 1 item selected 1.20 KB
Type here to search
6:27 PM
3/2/2026
To direct input to this VM, move the mouse pointer inside or press Ctrl+G.
Search
6:27 PM
3/2/2026