
## **OSPF Topology (Online Exam)**

Name: Devopriya Tirtho | ID: 160204033



- Area Should be Zero for all network and OSPF ID is 1 for all network too!!!
- Subnet by default Class C [255.255.255.0]

## **Addressing Table**

Device	Interface	IP Address	<b>Subnet Mask</b>	Default
				Gateway
Router 0	Fa0/0	211.146.1.2	255.255.255.0	N/A
	Se2/0	211.146.2.1	255.255.255.0	N/A
Router 1	Fa0/0	211.146.5.1	255.255.255.0	N/A
	Se2/0	211.146.2.2	255.255.255.0	N/A
	Se3/0	211.146.3.1	255.255.255.0	N/A
Router 2	Fa0/0	211.146.7.1	255.255.255.0	N/A
	Se2/0	211.146.3.2	255.255.255.0	N/A
	Se3/0	211.146.4.1	255.255.255.0	N/A
Router 3	Fa0/0	211.146.8.1	255.255.255.0	N/A
	Se2/0	211.146.4.2	255.255.255.0	N/A
Router 4	Fa0/0	211.146.1.1	255.255.255.0	N/A
	Fa1/0	211.146.0.1	255.255.255.0	N/A
Router 5	Fa0/0	211.146.5.2	255.255.255.0	N/A
	Fa1/0	211.146.6.1	255.255.255.0	N/A
Router 6	Fa0/0	211.146.7.2	255.255.255.0	N/A
	Fa1/0	211.146.6.2	255.255.255.0	N/A
Router 7	Fa0/0	211.146.8.2	255.255.255.0	N/A
	Fa1/0	211.146.9.1	255.255.255.0	N/A
PC 0	N/A	211.146.0.2	255.255.255.0	211.146.0.1
PC 1	N/A	211.146.0.3	255.255.255.0	211.146.0.1

PC 2	N/A	211.146.9.2	255.255.255.0	211.146.9.1
PC 3	N/A	211.146.9.3	255.255.255.0	211.146.9.1

## Configuration

Device	Command
R0	Router>enable
	Router#config t
	Enter configuration commands, one per
	line. End with CNTL/Z.
	Router(config)#router ospf 1
	Router(config-router)#network 211.146.1.0
	0.0.0.255 area 0
	Router(config-router)#network 211.146.2.0
	0.0.0.255 area 0
	Router(config-router)#exit
<b>R</b> 1	Router>enable
	Router#config t
	Enter configuration commands, one per
	line. End with CNTL/Z.
	Router(config)#router ospf 1
	Router(config-router)#network 211.146.3.0
	0.0.0.255 area 0
	Router(config-router)#network 211.146.5.0
	0.0.0.255 area 0
	Router(config-router)#network 211.146.2.0
	0.0.0.255 area 0
	Router(config-router)#exit
R2	Router>enable
	Router#config t
	Enter configuration commands, one per
	line. End with CNTL/Z.
	Router(config)#router ospf 1
	Router(config-router)#network 211.146.3.0
	0.0.0.255 area 0
	Router(config-router)#network 211.146.7.0 0.0.0.255 area 0
	Router(config-router)#network 211.146.4.0 0.0.0.255 area 0
	Router(config-router)#exit

	D ( . 11
R3	Router>enable
	Router#config t
	Enter configuration commands, one per
	line. End with CNTL/Z.
	Router(config)#router ospf 1
	Router(config-router)#network 211.146.4.0
	0.0.0.255 area 0
	Router(config-router)#network 211.146.8.0
	0.0.0.255 area 0
	Router(config-router)#exit
R4	Router>enable
	Router#config t
	Enter configuration commands, one per
	line. End with CNTL/Z.
	Router(config)#router ospf 1
	Router(config-router)#network 211.146.1.0
	0.0.0.255 area 0
	Router(config-router)#network 211.146.0.0
	0.0.0.255 area 0
	Router(config-router)#exit
<b>R5</b>	Router>enable
	Router#config t
	Enter configuration commands, one per
	line. End with CNTL/Z.
	Router(config)#router ospf 1
	Router(config-router)#network 211.146.6.0
	0.0.0.255 area 0
	Router(config-router)#network 211.146.5.0
	0.0.0.255 area 0
	Router(config-router)#exit
<b>R6</b>	Router>enable
	Router#config t
	Enter configuration commands, one per
	line. End with CNTL/Z.
	Router(config)#router ospf 1
	Router(config-router)#network 211.146.6.0
	0.0.0.255 area 0
	Router(config-router)#network 211.146.7.0
	0.0.0.255 area 0
	Router(config-router)#exit
<b>R7</b>	Router>enable
	Router#config t
	Enter configuration commands, one per
	line. End with CNTL/Z.
	Router(config)#router ospf 1
	Router(config-router)#network 211.146.9.0
	0.0.0.255 area 0

	Router(config-router)#network 211.146.8.0 0.0.0.255 area 0 Router(config-router)#exit
--	---