PostgreSQL - ALTER TABLE Command

The PostgreSQL **ALTER TABLE** command is used to add, delete or modify columns in an existing table.

You would also use ALTER TABLE command to add and drop various constraints on an existing table.

Syntax

The basic syntax of ALTER TABLE to add a new column in an existing table is as follows -

```
ALTER TABLE table_name ADD column_name datatype;
```

The basic syntax of ALTER TABLE to **DROP COLUMN** in an existing table is as follows –

```
ALTER TABLE table_name DROP COLUMN column_name;
```

The basic syntax of ALTER TABLE to change the **DATA TYPE** of a column in a table is as follows –

```
ALTER TABLE table_name ALTER COLUMN column_name TYPE datatype;
```

The basic syntax of ALTER TABLE to add a **NOT NULL** constraint to a column in a table is as follows –

```
ALTER TABLE table_name MODIFY column_name datatype NOT NULL;
```

The basic syntax of ALTER TABLE to **ADD UNIQUE CONSTRAINT** to a table is as follows –

```
ALTER TABLE table_name
ADD CONSTRAINT MyUniqueConstraint UNIQUE(column1, column2...);
```

The basic syntax of ALTER TABLE to ADD CHECK CONSTRAINT to a table is as follows -

```
ALTER TABLE table_name
ADD CONSTRAINT MyUniqueConstraint CHECK (CONDITION);
```

The basic syntax of ALTER TABLE to **ADD PRIMARY KEY** constraint to a table is as follows –

```
ALTER TABLE table_name
ADD CONSTRAINT MyPrimaryKey PRIMARY KEY (column1, column2...);
```

The basic syntax of ALTER TABLE to **DROP CONSTRAINT** from a table is as follows –

```
ALTER TABLE table_name
DROP CONSTRAINT MyUniqueConstraint;
```

If you are using MySQL, the code is as follows -

```
ALTER TABLE table_name
DROP INDEX MyUniqueConstraint;
```

The basic syntax of ALTER TABLE to DROP PRIMARY KEY constraint from a table is as follows -

```
ALTER TABLE table_name
DROP CONSTRAINT MyPrimaryKey;
```

If you are using MySQL, the code is as follows -

```
ALTER TABLE table_name
DROP PRIMARY KEY;
```

Example

Consider our COMPANY table has the following records -

The following is the example to ADD a new column in an existing table -

```
testdb=# ALTER TABLE COMPANY ADD GENDER char(1);
```

Now, COMPANY table is changed and the following would be the output from SELECT statement -

```
id | name
          age address
                           | salary | gender
            32 | California
                              20000
 2 Allen
            25 Texas
                              15000
 3 Teddy
            23 Norway
                              20000
 4 | Mark | 25 | Rich-Mond
                           65000
 5 | David |
            27 Texas
                              85000
 6 Kim
          22 | South-Hall
                              45000
 7 | James | 24 | Houston
                              10000
(7 rows)
```

The following is the example to DROP gender column from existing table -

```
testdb=# ALTER TABLE COMPANY DROP GENDER;
```

Now, COMPANY table is changed and the following would be the output from SELECT statement -

```
id name
         age address
                         salary
            32 | California
1 Paul
                           20000
2 Allen
           25 | Texas
                           15000
3 | Teddy | 23 | Norway
                           20000
4 Mark
           25 Rich-Mond
                           65000
           27 | Texas
5 David
                           85000
           22 | South-Hall | 45000
6 Kim
7 James
          24 Houston
                           10000
```