Start 1 / 8


<u>Start</u>

REDWallet				
Accounts Send Settings About				
Device: <no device=""></no>		Refresh	ETH ▼	
My Addresses		Во	alance (ETH)	
Plug your key to start!	Send	Prev 5	Next 5	

Until a key is plugged and recognized all the selectors and buttons should be disabled.

Device connected 2 / 8


When hardware key is connected and recognized



- 1) When the hardware key is recognized the list of first 5 addresses is queried.
- 2) Addresses are displayed with a default <loading> balance.
- 3) Balances are queried, and the <loading> is replaced by the right number value once retrieved.

Addresses loaded 3 / 8


When hardware key is connected and recognized



- 1) When the hardware key is recognized the list of first 5 addresses is queried.
- Addresses are displayed with a default <loading> balance.
- 3) Balances are queried, and the <loading> is replaced by the right number value once retrieved.

Balances loaded 4 / 8

When balances are displayed



- "Send" button is enabled only when a line in the text-list is selected.
- · When "Send" button is clicked, the "Send" tab is activated, and its "From" field filled with the selected address.
- · "Show details" is a contextual menu leading to the block explorer web page for that address.

When filling a transaction sending form

REDWallet
Accounts Send Settings About
Sending: ETH
From Address: 0xd98dd045f700d12aa160f8a5049a8e 12.23 ETH More
To Address: 0x29e6865e69069c8f38724d734434 ▼ 236.00 ETH More
Amount to send: 1.23465 ETH
Network: Mainnet
Gas Price: 21 Gwei Help
Gas Limit: 21000 Help
Sign Transaction

- "To Address" is a drop-down widget containing all the loaded addresses from the key + their balance (balance is removed when such address is selected).
- · "More..." links open a block explorer web page on for that Eth address

Signing transaction 6 / 8

When waiting for user signing a transaction

REDWallet				
Accounts	Settings About \			
Sending:	ETH			
From Address:	0xd98dd045f700d12aa160f8a5049a8e 12.23 ETH More			
To Address:	0x29e6865e69069c8f38724d734434 ▼ 236.00 ETH More			
Amount to send:	1.23465 ETH			
Network:	Mainnet			
Gas Price:	21 Gwei Help			
Gas Limit:	21000 <u>Help</u>			
Waiting for confirmation from your Nano Ledger S key				

When the transaction is confirmed, a web page is opened on a blockexplorer to follow the transaction's outcome. The "Send" form is reset, and the tab selection moves back to "Balance"

Settings 7/8


When waiting for user signing a transaction

REDWallet	
Accounts Send Settings About	
Network:	Mainnet ▼
Default Gas Price:	21 Gwei
Servers:	Red Foundation nodes Infura nodes Localhost on port 80

Changes are saved automatically in a local config file (using system/options/cache folder)

About 8/8

About



A short disclaimer should be there as most people will not read the license.