

VLAN Trunking Protocol (VTP)

Wednesday, June 17, 2026 11:48 AM

Commands for Trunking Configuration:-

Server Switch:

-- to configure fa 0/1 as trunk port

```
enable
configure terminal
interface fastEthernet 0/1
switchport mode trunk
exit
exit
```

-- to view trunk ports

```
show interface trunk
```

Transparent Switch:

-- to configure fa 0/1 -2 as trunk ports

```
enable
configure terminal
interface range fastEthernet 0/1 -2
switchport mode trunk
exit
exit
```

-- to view trunk ports

```
show interface trunk
```

Client Switch:

-- to configure fa 0/1 as trunk port

```
enable
configure terminal
interface fastEthernet 0/1
switchport mode trunk
```

exit
exit

-- to view trunk ports

show interface trunk

Commands for VTP Configuration:-

Server Switch:

-- to configure VTP Server

enable
configure terminal
vtp mode server
vtp version 2
vtp domain ccna.com
vtp password cisco
exit

-- to view VTP

show vtp status

Transparent Switch:

-- to configure VTP Transparent

enable
configure terminal
vtp mode transparent
vtp version 2
vtp domain ccna.com
vtp password cisco
exit

-- to view VTP

show vtp status

Client Switch:

-- to configure VTP Client

```
enable
configure terminal
vtp mode client
vtp version 2
vtp domain ccna.com
vtp password cisco
exit
```

-- to view VTP

```
show vtp status
```

Commands for VLAN Configuration:-

Server Switch:

-- to configure VLAN 10

```
enable
configure terminal
vlan 10
name HR
exit
```

-- to configure VLAN 20

```
vlan 20
name Sales
exit
```

-- to configure VLAN 30

```
vlan 30
name Testing
exit
```

-- to configure VLAN 40

```
vlan 40
name Developer
exit
exit
```

-- to view VLANs

show vlan brief

Client Switch:

-- to assign access ports to the respective VLAN's

```
interface range fastEthernet 0/2 -3  
switchport access vlan 10  
exit
```

```
interface range fastEthernet 0/4 -5  
switchport access vlan 20  
exit
```

```
interface range fastEthernet 0/6 -7  
switchport access vlan 30  
exit
```

```
interface range fastEthernet 0/8 -9  
switchport access vlan 40  
exit
```

-- to view VLANs

show vlan brief