
PC-PT
PC0
Fa0
Fa1/1
Fa2/1
Fa0/0
Fa0/1
Switch-PT
Switch0
Router-PT
Router0
Fa0
PC-PT
PC1


Physical
Config
CLI
Attributes
IOS Command Line Interface
Bridging software.
X.25 software, Version 3.0.0.
4 FastEthernet/IEEE 802.3 interface(s)
2 Low-speed serial(sync/async) network interface(s)
32K bytes of non-volatile configuration memory.
63488K bytes of ATA CompactFlash (Read/Write)
Press RETURN to get started!
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up
Router>en
Router#config terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#aaa new-model
Router(config)#aaa authentication login default local
Router(config)#username dinanath password cisco
Router(config)#line vty 0 3
Router(config-line)#login authentication default
Router(config-line)#exit
Router(config)#
Copy
Paste


PC-PT
PC0
Fa0
Fa1/1
Fa2/1
Fa0/0
Fa0/1
Switch-PT
Switch0
Router-PT
Router0
Fa0
PC-PT
PC1


Command Prompt
Cisco Packet Tracer PC Command Line 1.0
C:\>telnet 192.168.10.5
Trying 192.168.10.5 ...Open
User Access Verification
Username: dinanath
Password:
Router>en

PC-PT
PC2
Fa0
Fa0/1
Fa2/1
Gig0/0/0
Gig0/0/1
ISR4331
Router1
Fa0
Server-PT
Server0
Fa1/1
Switch-PT
Switch1
Fa0
PC-PT
PC3


Physical
Config
CLI
Attributes
IOS Command Line Interface
3207167K bytes of flash memory at bootflash:.
0K bytes of WebUI ODM Files at webui:.
Press RETURN to get started!
%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/0/1, changed state to up
Router>en
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#tacacs-server host 200.60.10.1
Router(config)#tacacs-server key 5678
Router(config)#aaa new-model
Router(config)#tacacs-server key 1234
Router(config)#aaa new-model
Router(config)#aaa authentication login default group tacacs local
Router(config)#line vty 0 3
Router(config-line)#login authentication default
Router(config-line)#exit
Router(config)#

PC-PT
PC2
Fa0
Fa0/1
Fa2/1
Gig0/0/0
Gig0/0/1
ISR4331
Router1
Fa0
Server-PT
Server0
Fa1/1
Switch-PT
Switch1
Fa0
PC-PT
PC3


Physical
Config
Desktop
Programming
Attributes
Command Prompt
C:\>
C:\>
C:\>
C:\>
C:\>
C:\>telnet 192.168.20.5
Trying 192.168.20.5 ...Open
User Access Verification
Username: dinanath
Password:
Router>
Router>
Router>
Router>
Router>
Router>
Router>
Router>
Router>
Router>
Router>
Router>
Router>
Router>!

Name: _____ Regd No: _____


PC-PT
PC4
Fa0
Fa0/1
Fa2/1
Gig0/0/0
Fa1/1
Switch-PT
Switch2
ISR4321
Router2
Fa0
PC-PT
PC5


IOS Command Line Interface
%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/0/0, changed state to up
ip address 192.168.30.5 255.255.255.0
Router(config-if)#ip address 192.168.30.5 255.255.255.0
Router(config-if)#exit
Router(config)#Hostname dinanath
dinanath(config)#ip domain name cisco.com
dinanath(config)#crypto key generate RSA
The name for the keys will be: dinanath.cisco.com
Choose the size of the key modulus in the range of 360 to 4096 for your
General Purpose Keys. Choosing a key modulus greater than 512 may take
a few minutes.
How many bits in the modulus [512]: 1024
% Generating 1024 bit RSA keys, keys will be non-exportable...[OK]
dinanath(config)#username dash password cisco
*Mar 1 0:3:22.900: %SSH-5-ENABLED: SSH 1.99 has been enabled
dinanath(config)#aaa new-model
dinanath(config)#aaa authentication login default local
dinanath(config)#line vty 0 3
dinanath(config-line)#login authentication default
dinanath(config-line)#transport input SSH
dinanath(config-line)#exit
dinanath(config)#enable password 1234
dinanath(config)#


PC-PT
PC4
Fa0
Fa0/1
Fa2/1
Gig0/0/0
Fa1/1
Switch-PT
Switch2
ISR4321
Router2
Fa0
PC-PT
PC5


Cisco Packet Tracer PC Command Line 1.0
C:\>SSH -l dash 192.168.30.5
Password:
dinanath>en
Password:
dinanath#conf t
Enter configuration commands, one per line. End with CNTL/Z.
dinanath(config)#!


PC-PT
PC6
Fa1/1
Fa2/1
Gig0/0/0
Gig0/0/1
Fa0
Switch-PT
Switch3
ISR4321
Router3
Server-PT
Server1
Fa0/1
PC-PT
PC7


Physical
Config
CLI
Attributes
IOS Command Line Interface
Router(config)#Hostname mac
mac(config)#ip domain name cisco.com
mac(config)#crypto key generate RSA
The name for the keys will be: mac.cisco.com
Choose the size of the key modulus in the range of 360 to 4096 for your
General Purpose Keys. Choosing a key modulus greater than 512 may take
a few minutes.
How many bits in the modulus [512]: 1024
% Generating 1024 bit RSA keys, keys will be non-exportable...[OK]
mac(config)#username dash
*Mar 1 0:4:19.425: %SSH-5-ENABLED: SSH 1.99 has been enabled
mac(config)#username dash password cisco
mac(config)#aaa new-model
mac(config)#aaa authentication login default local
mac(config)#tacacs-server host 200.60.20.1
mac(config)#tacacs-server key 5678
mac(config)#aaa authentication login default group tacacs local
mac(config)#line vty 0 3
mac(config-line)#login authentication default
mac(config-line)#transport input SSH
mac(config-line)#exit
mac(config)#enable password 0987
mac(config)#

PC-PT
PC2
Fa0
Fa0/1
Fa2/1
Gig0/0/0
Gig0/0/1
Fa0
Fa1/1
Switch-PT
Switch1
ISR4331
Router1
Server-PT
Server0
Fa0
PC-PT
PC3


Physical
Config
Desktop
Programming
Attributes
Command Prompt
Cisco Packet Tracer PC Command Line 1.0
C:\>SSH -l dinanath 192.168.20.5
Password:
% Login invalid
Password:
A>en
Password:
A#conf t
Enter configuration commands, one per line. End with CNTL/Z.
A(config)#

Name: _____ Regd No: _____