


Ventura, Robert R.


C335IT

2023-1-01666

October 14, 2025



Visit <https://www.mysql.com/downloads/> and click on [MySQL Community \(GPL\) Downloads »](#)



Click on [MySQL Installer for Windows](#)

[General Availability \(GA\) Releases](#)[Archives](#)[?](#)

MySQL Installer 8.0.43

**Note:** MySQL 8.0 is the final series with MySQL Installer. As of MySQL 8.1, use a MySQL product's MSI or Zip archive for installation. MySQL Server 8.1 and higher also bundle MySQL Configurator, a tool that helps configure MySQL Server.

Select Version:

8.0.43

Select Operating System:


Microsoft Windows

Windows (x86, 32-bit), MSI Installer (mysql-installer-web-community-8.0.43.0.msi)	8.0.43	2.1M	Download
MD5: 0d067e364c208122e7fc62ecbf00d985 Signature			
Windows (x86, 32-bit), MSI Installer (mysql-installer-community-8.0.43.0.msi)	8.0.43	354.3M	Download
MD5: af62a4e2c58b5013bb5e75531e088b29 Signature			


 We suggest that you use the [MD5 checksums](#) and [GnuPG signatures](#) to verify the integrity of the packages you download.

Windows (x86, 32-bit), MSI Installer	8.0.43	354.3M	Download
(mysql-installer-community-8.0.43.0.msi)	MD5: af62a4e2c58b5013bb5e75531e088b29 Signature		

Click on the second one



Wait for it to finish



After setting it up, click on full and there you go.

MySQL Installer

MySQL Server 8.0.43

Type and Networking

Authentication Method

Accounts and Roles

Windows Service

Server File Permissions

Apply Configuration

Type and Networking

Server Configuration Type

Choose the correct server configuration type for this MySQL Server installation. This setting will define how much system resources are assigned to the MySQL Server instance.

Config Type: Development Computer

Connectivity

Use the following controls to select how you would like to connect to this server.

☒ TCP/IP

Port: 3306X Protocol Port: 33060

☒ Open Windows Firewall ports for network access

☐ Named Pipe

Pipe Name: MYSQL

☐ Shared Memory

Memory Name: MYSQL

Advanced Configuration


Select the check box below to get additional configuration pages where you can set advanced and logging options for this server instance.

☐ Show Advanced and Logging Options

Next >

Cancel

Configure.



Choose the recommended