## **SAP FI-SD Integration**

- 1. Define Sales Organization
- 2. Assign Sales Organization to Company Code
- 3. Define Distribution Channel
- 4. Assign Distribution channel to Sales Organization
- 5. Define Division
- 6. Assign Division to Sales Organization
- 7. Define Plant
- 8. Define Shipping Point
- 9. Assign Shipping Point to Plant
- 10. Maintain Sales Area
- 11. Assign Sales Organization-Distribution Channel-Plant

# Define Sales Organization | Create sales Organization SAP SD

Sales organizations are defined in SAP based on the company sales requirement. Sales organization controls terms of sales to the customers, negotiating sales, etc. It can be assigned to only one company code and one or more plants.

## Configuration of Sales Organization in SAP SD


IMG Menu Path:-

SPRO -> Implementation Guide -> Enterprise Structure -> Definition -> Sales and Distribution -> Define, copy, delete, check Sales organization -> Define Sales organization


T Code to Define Sales Organisation:- OVX5

## Steps to Create New Sales Organization in SAP


Step 1:- Enter Transaction Code SPRO in the Command field and press Enter



Step 2:- In the next screen, click on SAP Reference IMG




**Step 3:-** In the next screen, follow the menu path for Define sales organization




Step 4:- A window will pop up and Double click on Define sales Organization

5 Up 4110 2 0 0 0 10 0 11 0 11 2 0 11110 0 0 1 0 0 1 0 0 1 1 1 1									
Choose Activity									
Name of Activity									
Define Sales Organization									
Copy, delete, check sales organization									

**Step 5:-** In the next screen, click on New Entries




Step 6:- Update the sales organization key and name of the sales organization.



## Step 7:-


Press enter and click on the save icon; another window will pop up for updating the address. Update the sales organization address.



Thus Sales Organization is successfully configured in SAP SD.

## How to Assign Sales Organization to Company Code


IMG Menu Path: - SPRO > IMG > Enterprise structure > Assignment > Sales and Distribution > assign sales org to company code



Select position and update sales organization code and press enter



Update company code in the CoCd field and press enter



Click on save icon to save the configured data. Thus sales organization is successfully assigned to company code.

### How to Create Distribution channel in SAP SD

## Steps to Create Distribution Channel


#### IMG Menu Path:-

SPRO > Customizing Implementation Guide > Enterprise Structure > Definition > Sales and Distribution > Define, copy, delete, check Distribution channel

## T Code for Define Distribution channel:- OVXI


#### **Step 1:-**

Enter T Code SPRO in the Command field and press enter from the keyboard



Step 3:-

Follow the IMG menu path as per the below screenshot to define the distribution channel.




#### Step 4:-

Click on Define, copy, delete, check Distribution channel, a pop-up window will be displayed, and select a Distribution channel.




## Step 5:-

In the next screen, change the view distribution channels overview screen, click on new entries to create a new distribution channel.



Step 6:-

Enter Distribution channel key in the Distr. Channel field and give the name of the distribution channel.



## **Step 7:-**

Click on the save icon to save the configuration settings



Thus distribution channel is successfully created in SAP SD

# Assign Distribution Channel to Sales Organization in SAP

The following SAP tutorial guides you how to assign distribution to sales organization in SAP. The Distribution channels are assigned to sales organization by using following navigation method

- IMG Path :- SPRO > IMG > Enterprise structure > Assignment > Sales and distribution > Assign distribution Channel to sales organization
- Transaction code: OVXKN

In this Activity, we are going to assign sales organization to the following distribution channels

Sales Organization

Distribution Channel

AD06 10 AD06 20 AD06 30

## Prerequisites to assign distribution channel to Sales Organization

- Define Distribution channel
- Define Sales Organization

Distribution channel represents channels of an organization to distribute goods or services to customer. Sales Organization controls all the activities of sales in an organization.

# How to assign distribution channel to sales organization in SAP system


Step 1: Enter SAP T-code" OVXKN" in the SAP Command field

**Step 2:** On change view "Assignment Sales Organization – Distribution channel screen, click on **new entries** for assignment of distribution channel to sales organization in SAP



Step 3: On New Entries of Assignment screen, update the following details

- **SOrg:** Enter Sales organization key for assigning with distribution channel
- **DChl**: Enter distribution Channel for assign to sales organization, press enter key to validate the data by system.



After assignment of Sales organization to distribution channel, click on save icon to save the configured data. Successfully we have assigned distribution Channel to sales organizations in SAP. Continue to read free SAP SD tutorials and materials.

## How to Create Division in SAP | Define Division


## **Steps to Create Division in SAP:-**

## IMG Menu Path:-


SPRO > SAP Customizing Implementation Guide > Enterprise Structure > Definition > Logistics-General > Define, copy, delete, check division

T Code to Define Division in SAP:- OVXB


**Step 1:-** Enter Transaction Code SPRO in the command field and press enter from the keyboard.




**Step 3:-** Follow the IMG menu path to define a new division in SAP and click on execute Define copy, delete, check division.




Step 4:- In the next screen, a popup window will be displayed; click on Define Division.



Step 5:- Click on New entries to create divisions.



**Step 6:**– Enter the division key in the division field and update the division name.



**Step 7:-** Click on the Save icon to save the inputs



Thus New Division is successfully configured in SAP

# How to Assign Division to Sale Organization in SAP


The following SAP tutorial guides you how to assign division to sales Organization in SAP step by step. The integration between division and sales organization in sap established through this assignments of divisions and sales organization.

Before assignment of division to sales organization in SAP, you need to define

- Division in SAP
- Sales Organization in SAP

You can assign division to sales organization in SAP by using the following navigation method

- Transaction code: OVXAN
- IMG menu path :- SPRO > SAP Implementation guide > Enterprise structure > Assignment > Sales and Distribution > Assign Division to Sales Org.



## <u>Configuration steps: –</u>


**Step 1:** Enter T-Code "OVXAN" in SAP command field or follow the SAP IMG path Enterprise Structure – Assignment – Sales and Distribution and execute "Assign Division to Sales Organization".

**Step 2:** On change view "Assignment Sales Organization – Division" overview screen, click on new entries to assign divisions to sales organizations.



**Step 4:** To Assign Division to Sales Organization in SAP, on new entries screen, update the following details: –

- Sales Organization: Update sales organization code in the SOrg. field and
- **Division:** Division code in the Dv field, after updating press enter to continue



After assigning all the divisions to the sales organization, click on save icon to save the configured data.


## Steps to Define Plant:-

## **IMG Menu Path:**-


SPRO > SAP Customizing Implementation Guide (IMG) > Enterprise Structure > Definition > Logistics – General > Define copy, delete, check plant

**Transaction Code to Define Plant:- OX10** 


**Step 1:-** Enter Transaction Code SPRO in the command field and press enter.



Step 2:- Click on SAP Reference IMG




**Step 3:-** Follow the Menu Path as per the below screenshot



Step 4:- Click on Define Plant




**Step 5:-** Click on New Entries



**Step 6:-** Enter new plant code and update the name of the Plant, and press enter.

New Entries: Details of Added Entries							
Plant	ADE						
Name 1	ADE - Bangalore						
Name 2							
Detailed informat	tion						
Language Key							
House number/s	street						
PO Box							
Postal Code							
City							
Country Key							
Region							
County code							
City code							
Tax Jurisdiction							
Factory calendar							

**Step 7:-** Update the address of the plant and press enter.



**Step 8:-** After updating all mandatory fields, click on the save icon



Thus Plant was successfully configured in SAP.

# How to Define Shipping Point in SAP | Create Shipping Point

**About Shipping Point:-** Shipping Point is an organizational element where the shipping activities are executed. We can assign shipping point to more than one plant.

### Step by Step defining shipping point in SAP:-

Transaction Code to create shipping point in SAP:- OVXD


#### IMG Menu Path:-

SAP Customizing Implementation Guide > Enterprise Structure > Definition > Logistic Execution > Define, Copy, Delete, check Shipping Point

**Step 1:-** Enter Transaction code SPRO in the command field and press enter from keyboard.




Step 2:- Click on SAP Reference IMG




Step 3:- Follow the Menu path as per the below screenshot and click on Define, Copy, Delete, check Shipping Point.



**Step 4:-** Shipping point can be created by two methods either copying the exiting shipping point for creating a new one, here we are creating a new shipping point. Double click on the defined shipping point



**Step 5:-** In the next screen, a list of existing shipping points will be displayed; click on New entries for defining new shipping points.




**Step 6:-** Next, update the required data for the defining shipping point-

**Shipping Point:**— Enter the new shipping point key and update the description of the shipping point **Times:**- Update the Factory calendar and working times

Determine Time:- Update the determined Load time, determine to pick and pack time, and rounding working days

Shipping Point BANG	Shipping Point Bangalore
Location	
Country	Departure Zone
Times	
Factory Calendar IN IN	NDIAN CALENDAR
Working Times	
Determine Times	
Determine Load. Time No	loading time determination
Det.Pick/Pack Time	ck/pack time not determined
Det.Pick/Pack Time	cr/pack time not determined
Rounding Work Days	
Rounding Work Days Form Text Names	Print Picking List
ter	Print Picking List Output Type
Form Text Names	
Form Text Names Address Text Name	Output Type
Form Text Names Address Text Name Letter Header Text	Output Type  Message Language
Form Text Names Address Text Name Letter Header Text Text Name Foot.Unes	Output Type  Message Language  Number of Messages
Form Text Names Address Text Name Letter Header Text Text Name Foot.Lines Text Name Greeting	Output Type  Message Language  Number of Messages  Send Time
Form Text Names  Address Text Name  Letter Header Text  Text Name Foot.Lines  Text Name Greeting  Text Name SDB Sender	Output Type  Message Language  Number of Messages  Send Time  Transmission Medium
Form Text Names Address Text Name Letter Header Text Text Name Foot.Lines Text Name Greeting	Output Type  Message Language  Number of Messages  Send Time  Transmission Medium  Subsystem

After updating the required data, press Enter from Key Board, a pop-up window for the address will be opened



Step 7:- After Updating the address for the shipping point, click on the save icon




Thus Shipping Point is successfully configured in SAP.


# How to assign shipping point to plant

Access the transaction by using the following navigation option.


SAP IMG Path: SPRO >> IMG >> Enterprise Structure >> Assignment >> Logistic Execution >> **Assign Shipping Point to Plant** 



Select the find button to search for plant



Enter plant in the find field and select plant from the list



Click on assign button and select shipping point from the list. Press enter



Click on save button to the data. Successfully you have assigned shipping point to plant.

Shipping Points -> Plants: Overview								
A	Assign	Analyze error(s)	Delete	Select/Deselect	Deselect			
Plant Shipping Points								
ADI	E ADE	- Bangalore		L L				
BANG Shipping Point Bangalore								

Successfully shipping point is assigned to a plant.

# **How to Create Sales Area in SAP SD**


#### **Steps to Create Sales Area in SAP:-**

## **IMG Menu path:**-

SPRO > SAP Customizing Implementation Guide > Enterprise Structure > Assignment > Sales and Distribution > Set up Sales Area


## Step 1:-

Enter Transaction Code SPRO in the Command Field




#### Step 2:

Click on SAP Reference IMG



### Step 3:-

Follow the Menu Path and click on Set up Sales Area execute Icon.




## Step 4:-

Click on New entries for Assignment between Sales Organisation, Distribution Channel, and Division.



Step 5:- Enter the following details and Enter

- Update Sales Organisation key in the SOrg. field
- 2. Update the distribution channel key in the Dchl field and
- 3. Update division key in the DV field





# How to assign sales organization and distribution channel to plant


The following SAP tutorials guides you how to assign sales organization /distribution channel to plant in SAP step by step.

The assignment of sales organization and distribution channel to plant enables the link between the sales organization, distribution channel and plant in SAP system.


*In this activity, We are going to assign Sales Organization-AD06* + *Distribution Channel-10* to *Plant-ADE*.

**Step 1:** To assign sales organization, distribution channel to plant key by using the following navigation method

- Transaction code: SPRO
- SAP IMG Path: SPRO > IMG > Enterprise Structure > Assignment > Sales & Distribution > Assign Sales organization/Distribution channel to Plant




**Step 2:** On the change view "assignment sales organization /distribution channel -plant, select **new entries** for assignment of Sales Organization/Distribution channel to Plant.



Step 3: On new entries: overview of added entries screen, enter the following fields.

- Enter sales organization key in sales org field
- Enter distribution channel in the distribution channel/mt field
- Enter plant code in the plant field



Click on save icon to save the data. Successfully you have assigned sales organization/distribution channel to plant.