

SW-Access:

```
Switch>enable
Switch#configure terminal
Enter configuration commands, one per line.  End with CNTL/Z.
Switch(config)#vlan 10
Switch(config-vlan)#name STAFF
Switch(config-vlan)#exit
Switch(config)#vlan 20
Switch(config-vlan)#name STUDENT
Switch(config-vlan)#exit
Switch(config)#interface fastEthernet0/2
Switch(config-if)#switchport mode access
Switch(config-if)#switchport access vlan 10
Switch(config-if)#exit
Switch(config)#interface fastEthernet0/3
Switch(config-if)#switchport mode access
Switch(config-if)#switchport access vlan 20
Switch(config-if)#exit
Switch(config)#interface range fastEthernet0/4 - 6
Switch(config-if-range)#switchport mode access
Switch(config-if-range)#spanning-tree portfast
%Warning: portfast should only be enabled on ports connected to a single
host. Connecting hubs, concentrators, switches, bridges, etc... to this
interface when portfast is enabled, can cause temporary bridging loops.
Use with CAUTION

%Portfast has been configured on FastEthernet0/4 but will only
have effect when the interface is in a non-trunking mode.
%Warning: portfast should only be enabled on ports connected to a single
host. Connecting hubs, concentrators, switches, bridges, etc... to this
interface when portfast is enabled, can cause temporary bridging loops.
Use with CAUTION

%Portfast has been configured on FastEthernet0/5 but will only
have effect when the interface is in a non-trunking mode.
%Warning: portfast should only be enabled on ports connected to a single
host. Connecting hubs, concentrators, switches, bridges, etc... to this
interface when portfast is enabled, can cause temporary bridging loops.
Use with CAUTION

%Portfast has been configured on FastEthernet0/6 but will only
have effect when the interface is in a non-trunking mode.
Switch(config-if-range)#exit
Switch(config)#interface gigabitEthernet0/1
Switch(config-if)#switchport mode trunk

Switch(config-if)#
%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/1,
changed state to down
```

%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/1, changed state to up

```
Switch(config-if)#switchport trunk allowed vlan 10,20
Switch(config-if)#exit
Switch(config)#end
Switch#
%SYS-5-CONFIG_I: Configured from console by console
```

```
Switch#write memory
Building configuration...
[OK]
Switch#show vlan brief
```

VLAN Name	Status	Ports
-----	-----	-----
1 default	active	Fa0/1, Fa0/4, Fa0/5, Fa0/6 Fa0/7, Fa0/8, Fa0/9, Fa0/10 Fa0/11, Fa0/12, Fa0/13, Fa0/14 Fa0/15, Fa0/16, Fa0/17, Fa0/18 Fa0/19, Fa0/20, Fa0/21, Fa0/22 Fa0/23, Fa0/24, Gig0/2
10 STAFF	active	Fa0/2
20 STUDENT	active	Fa0/3
1002 fddi-default	active	
1003 token-ring-default	active	
1004 fddinet-default	active	
1005 trnet-default	active	

```
Switch#show interfaces trunk
```

Port	Mode	Encapsulation	Status	Native vlan
Gig0/1	on	802.1q	trunking	1

Port	Vlans allowed on trunk
Gig0/1	10,20

Port	Vlans allowed and active in management domain
Gig0/1	10,20

Port	Vlans in spanning tree forwarding state and not pruned
Gig0/1	10,20

```
Switch#
```