```
Help
#include "bsdisdiv1d.h"
#include "chk.h"
#include "error_msg.h"
#include "model.h"
#include "pnl/pnl_matrix.h"
extern char* path_sep;
static int MOD(Init)(Model *model)
  TYPEMOD* pt=(TYPEMOD*)(model->TypeModel);
  if (model->init == 0 )
    {
      model->init = 1;
      model->nvar=0;
      pt->T.Vname = "Current Date";
      pt->T.Vtype=DATE;
      pt->T.Val.V_DATE=0.;
      pt->T.Viter=ALLOW;
      model->nvar++;
      pt->Size.Vname = "Number of Discrete Dividends";
      pt->Size.Vtype=PINT;
      pt->Size.Val.V PINT=1;
      pt->Size.Viter=FORBID;
      model->nvar++;
      pt->S0.Vname = "Spot";
      pt->S0.Vtype=PDOUBLE;
      pt->S0.Val.V_PDOUBLE=100.;
      pt->SO.Viter=ALLOW;
      model->nvar++;
      pt->Mu.Vname = "Trend";
      pt->Mu.Vtype=DOUBLE;
      pt->Mu.Val.V DOUBLE=0.;
      pt->Mu.Viter=ALLOW;
      model->nvar++;
```

```
pt->Sigma.Vname = "Volatility";
    pt->Sigma.Vtype=PDOUBLE;
    pt->Sigma.Val.V PDOUBLE=0.2;
    pt->Sigma.Viter=ALLOW;
   model->nvar++;
    pt->R.Vname = "Annual Interest Rate";
    pt->R.Vtype=DOUBLE;
    pt->R.Val.V_DOUBLE=10.;
    pt->R.Viter=ALLOW;
   model->nvar++;
    pt->Amounts.Vname = "Dividend Amounts";
    pt->Amounts.Vtype=PNLVECT;
    pt->Amounts.Val.V_PNLVECT=NULL;
    pt->Amounts.Viter=FORBID;
    model->nvar++;
   pt->Dates.Vname = "Dividend Dates";
    pt->Dates.Vtype=PNLVECT;
    pt->Dates.Val.V_PNLVECT=NULL;
    pt->Dates.Viter=FORBID;
   model->nvar++;
  }
if (pt->Amounts.Val.V PNLVECT==NULL){
  if ((pt->Amounts.Val.V PNLVECT=
       pnl_vect_create_from_double (pt->Size.Val.V_PINT,
  3.0)) == NULL)
    goto err;
}
if(pt->Dates.Val.V_PNLVECT==NULL){
  if ((pt->Dates.Val.V PNLVECT=
       pnl_vect_create_from_double (pt->Size.Val.V_PINT,0
  .5))==NULL)
    goto err;
}
/* pt->Size.Val.V_INT = pt->S0.Val.V_PNLVECT->size;*/
```

```
return OK;
 err:
 Fprintf(TOSCREEN, "%s{n", error_msg[MEMORY_ALLOCATION_FAILU
    RE]);
 exit(WRONG);
}
static int MOD(Get)(int user,Planning *pt_plan,Model *
   model)
{
  int nvar;
  TYPEMOD *pt=(model->TypeModel);
 VAR *var = ((VAR*) pt);
  int i;
 model->Init(model);
 nvar = model->nvar;
  if (user==TOSCREEN)
    if ((model->Show)(user,pt plan,model))
      do
         Fprintf(TOSCREEN,"_____
    Model:%s{n",model->Name);
          ScanVar(pt plan, user, &(pt->Size));
         pnl_vect_resize_from_double(pt->Amounts.Val.V_PN
    LVECT, pt->Size.Val.V PINT, 3.0);
          pnl_vect_resize_from_double(pt->Dates.Val.V_PNLV
    ECT, pt->Size.Val.V PINT, 0.5);
          for (i=1; i<nvar; i++)</pre>
              ScanVar(pt_plan,user,&(var[i]));
            }
      while ((model->Show)(user,pt_plan,model));
  return ((model->Show)(TOSCREENANDFILE,pt plan,model));
}
```

```
static int MOD(FGet)(char **InputFile,int user,Planning *pt
   _plan,Model *model)
₹
 int nvar;
 TYPEMOD *pt=(TYPEMOD*)(model->TypeModel);
 VAR *var = ((VAR*) pt);
 int i;
 model->Init(model);
 nvar = model->nvar;
 if (user==TOSCREEN)
   if ((model->Show)(user,pt plan,model))
     do
         Fprintf(TOSCREEN,"_____
   Model:%s{n",model->Name);
         FScanVar(InputFile, pt_plan, user, &(pt->Size));
         pnl vect resize from double(pt->Amounts.Val.V PN
   LVECT, pt->Size.Val.V PINT,3.0);
         pnl_vect_resize_from_double(pt->Dates.Val.V_PNLV
   ECT, pt->Size.Val.V_PINT,0.5);
         for (i=1; i<nvar; i++)
             FScanVar(InputFile,pt plan,user,&(var[i]));
           }
       }
     while ((model->Show)(user,pt_plan,model));
 return ((model->Show)(TOSCREENANDFILE,pt plan,model));
}
/**
* Check function for BSDISDIV1D
* @param user:
* @param pt_plan:
* Oparam model: the model to be checked
```

```
* general model check function
*/
int MOD(Check)(int user,Planning *pt_plan,Model *model)
{
  VAR *var;
  void* pt=(model->TypeModel);
  int status=OK;
  int i, nvar=0;
  char helpfile[MAX_PATH_LEN]="";
  if ((2*strlen(model->ID)+strlen("{{mod{{"}} +strlen("{{{"}}})
       +strlen("_doc.pdf"))>=MAX_PATH_LEN)
      Fprintf(TOSCREEN, "%s{n", error_msg[PATH_TOO_LONG]);
      exit(WRONG);
    }
  strcpy(helpfile,path sep);
  strcat(helpfile, "mod");
  strcat(helpfile,path_sep);
  strcat(helpfile,model->ID);
  strcat(helpfile,path_sep);
  strcat(helpfile,model->ID);
  strcat(helpfile,"_doc.pdf");
  nvar = model->nvar;
  var = ((VAR*) pt);
  for (i=0; i<nvar; i++)</pre>
      status+=ChkVar(pt_plan, &(var[i]));
      if (var[i].Vtype==PNLVECT && var[i].Val.V PNLVECT->si
    ze != ((BSDISDIV1D*)pt)->Size.Val.V_PINT)
        status += 1;
  return Valid(user,status,helpfile);
}
```

```
TYPEMOD BlackScholesDisDiv1dim;
MAKEMOD_FULL(BlackScholesDisDiv1dim);
```

References