Infor VISUAL API Toolkit Database Registration Guide

Copyright © 2024 Infor

Important Notices

The material contained in this publication (including any supplementary information) constitutes and contains confidential and proprietary information of Infor.

By gaining access to the attached, you acknowledge and agree that the material (including any modification, translation or adaptation of the material) and all copyright, trade secrets and all other right, title and interest therein, are the sole property of Infor and that you shall not gain right, title or interest in the material (including any modification, translation or adaptation of the material) by virtue of your review thereof other than the non-exclusive right to use the material solely in connection with and the furtherance of your license and use of software made available to your company from Infor pursuant to a separate agreement, the terms of which separate agreement shall govern your use of this material and all supplemental related materials ("Purpose").

In addition, by accessing the enclosed material, you acknowledge and agree that you are required to maintain such material in strict confidence and that your use of such material is limited to the Purpose described above. Although Infor has taken due care to ensure that the material included in this publication is accurate and complete, Infor cannot warrant that the information contained in this publication is complete, does not contain typographical or other errors, or will meet your specific requirements. As such, Infor does not assume and hereby disclaims all liability, consequential or otherwise, for any loss or damage to any person or entity which is caused by or relates to errors or omissions in this publication (including any supplementary information), whether such errors or omissions result from negligence, accident or any other cause.

Without limitation, U.S. export control laws and other applicable export and import laws govern your use of this material and you will neither export or re-export, directly or indirectly, this material nor any related materials or supplemental information in violation of such laws, or use such materials for any purpose prohibited by such laws.

Trademark Acknowledgements

The word and design marks set forth herein are trademarks and/or registered trademarks of Infor and/or related affiliates and subsidiaries. All rights reserved. All other company, product, trade or service names referenced may be registered trademarks or trademarks of their respective owners.

Publication Information

Release: Infor VISUAL API Toolkit

Publication date: August 13, 2024

Contents

About this guide **4**

Intended audience 4

Related documents 4

Contacting Support ..... **Error! Bookmark not defined.**

Support information 5

Connecting a VISUAL database **6**

Registering a VISUAL database 6

Reviewing registered database information 7

Changing the VISUAL executable path 7

Unregistering a VISUAL database 7

Testing the connection to Toolkit components 8

Viewing documentation 8

Viewing available Toolkit components 8

About this guide

This guide describes how to establish a connection to a VISUAL database for the purpose of using the API Toolkit.

Intended audience

The intended audience of this guide is developers who are using the API Toolkit to extend the VISUAL solution.

Related documents

You can find the document in the product documentation section of the Infor Xtreme Support portal, as described in "Contacting Infor."

Infor VISUAL API Toolkit Development Guide

Infor VISUAL API Toolkit Financial Class Library Reference

Infor VISUAL API Toolkit Inventory Class Library Reference

Infor VISUAL API Toolkit Purchasing Class Library Reference

Infor VISUAL API Toolkit Sales Class Library Reference

Infor VISUAL API Toolkit Shared Class Library Reference

Infor VISUAL API Toolkit Shop Floor Class Library Reference

Infor VISUAL API Toolkit Trace Class Library Reference

Contacting Support

If you have questions about Infor products, go to the Infor Customer Portal at https://customerportal.infor.com/csmcore/

If we update this document after the product release, we will post the new version on this Web site. We recommend that you check this Web site periodically for updated documentation.

If you have comments about Infor documentation, contact https://docs.infor.com/en-us.

Support information

The API Toolkit will be updated regularly as more class members are added to each assembly, schema changes are made, and any reported issues are resolved. Infor Support cannot assist you with developing customized code using the API Toolkit. For assistance with customizations, contact Infor Consulting Services or your channel partner.

The functionality provided within the API Toolkit will not be extended beyond the standard functionality experienced in the VISUAL application itself. Enhancement requests with compelling business cases detailing how suggested alternatives are not viable will be evaluated and considered.

Infor is not responsible for data incorrectly entered to the database through the use of the API Toolkit. Customers must establish a full test environment to ensure that data created by APIs functions in the same manner as data created through the VISUAL interface.

Connecting a VISUAL database

Before your customized code can interact with any of the API Toolkit's business logic libraries, you must first have a valid connection to a VISUAL Enterprise database. All database connectivity information is stored in an XML file named DATABASE.CONFIG. You can store an unlimited number of licensed VISUAL Enterprise databases in the configuration file.

Registering a VISUAL database

To register a VISUAL database:

1. Navigate to the directory where your VISUAL executables are stored.
2. Launch VmfgConfigForms.exe. In the left pane, any previously registered database instances are displayed. A green circle with a check mark indicates that the database connection is active and available.
3. Click **Register Database**.
4. Specify this information:

   Database Name – Specify the name of your VISUAL database.

   Provider – Specify the type of database engine you use. Select SQL Server or Oracle.

   Server Name – Specify the name of the server where the VISUAL database resides.

   Owner User ID – Specify SYSADM.

   Owner Password – Specify the password associated with the owner user ID.

   Verify Password – Re-type the password associated with the user ID.
5. Click **Next**. If a connection could not be made to the database, a message stating that the database could not be opened with the information provided is displayed. If you specified a database that is not at version 8.0.0 or later, a message stating that the database you selected cannot be registered is displayed. If a connection is made, then the Setup VISUAL Manufacturing Executable Path is displayed.
6. In the VISUAL Executable Path field, specify the location where your VISUAL executables are stored. The VISUAL executable path is used if your custom application results in the generation of BODs or if average costing is used in the VISUAL database. The path you specify is not validated. Make sure you specify the correct path.

7 Click **Next**. The name of the database you registered is displayed. The database information you specified is written to the DATABASE.CONFIG file.

8 Click **Ok.**

Reviewing registered database information

After you register a database, the name of the database is displayed in the left pane. If a connection can currently be made to the database, a green circle with a check box is displayed. If a connection cannot currently be made to the database, a red circle with an X is displayed. To review information about the database, click the database name. The database name, provider, server name, owner user ID, and VISUAL executable path is displayed.

Changing the VISUAL executable path

If the location of your VISUAL executables changes, you can update the executable path information. If you have registered multiple VISUAL databases, update the executable path for each database. To update the information:

1 In the left pane, select the database to update.

2 Click **Setup VISUAL Manufacturing Path**.

3 In the VISUAL Executable Path field, specify the location of your VISUAL executables.

4 Click **Ok**.

Unregistering a VISUAL database

If you no longer use a particular database with the API Toolkit, you can unregister the database. Unregistering the database makes it unavailable for use with the API Toolkit. Unregistering the database does not drop or detach the database from your database engine. An unregistered database is still available for use in the standard VISUAL product.

To unregister a database:

1 In the left pane, select the database to unregister.

2 Click **Unregister Database**.

3 Confirm that the name of the database you are unregistering is displayed.

4 Click **Next**. The database is unregistered.

Testing the connection to Toolkit components

To ensure that you can connect to the Toolkit components and that the components can communicate with your database properly, use the Test Database function.

To test the connections:

1. In the Databases pane, click the database to test.
2. Click **Test Database**. The components of the Toolkit are tested to ensure that they can communicate with your database.
3. After the tests are complete, click **Close**.

Viewing documentation

To view a list of available documents, select **Help > Documentation**. A list of guides and references is displayed. Click a link to open a document.

All documents are stored in your VISUAL executable directory.

Viewing available Toolkit components

To view a list of the components included in the Toolkit, select **Help > About**. A list of components is displayed.