CS341: Operating System

Computer System Architetcure from OS Design Prospective

Lect03: 5th Aug 2014

Dr. A. Sahu

Dept of Comp. Sc. & Engg.

Indian Institute of Technology Guwahati

Outline

- OS in one slide: Virtualized the Hardware and Manage
- Review of Computer Systems Architecture
- OS in one Lecture: Components of OS


Operating System in One Slide

- OS act an intermediary between: User and Hardware
- Operating system goals:
 - Execute user programs and make solving user problems easier
 - Make the computer system convenient to use
 - Use the computer hardware in an efficient manner
- A well-designed useful abstracted interfaces
 - Sockets, file systems, and address spaces into a single convenient package, Probably best contributions of CS
- Provides a virtual execution environment on top of hardware
 - That is more convenient than the raw hardware interface
 - More Simple, More reliable, More secure, More portable, More efficient......

Review
of
Computer System Architecture
from
OS Prospects

Computer System Organization

- Computer-system operation
 - One or more CPUs, device controllers connect through common bus providing access to shared memory
 - Concurrent execution of CPUs and devices competing for memory cycles



Every Motherboard Have

- Processor and Memory (Need to Add)
- Controller (Programmable & Now a day -Smarter)
 - DMA Controller (Ex IC 8237) {Simiar to Taxi wala}
 - Interrupt Controller (Ex IC 82C59) {PA to Director}
 - Timer (Example IC 82C54) {An alram }
 - USB Controller (Example IC 8251) \$Isusb
 - PCI Bus Controller \$Ispci
- All these devices have: Address to control, control register and status register

CS321: Computer Peripheral and Interface
How to write monitor or driver program in Assembly
Language using 8085 or in C using PIC Microcontroller

Computer-System Operation

- I/O devices and the CPU can execute concurrently
- Each device controller is in charge of a particular device type
- Each device controller has a local buffer
- CPU moves data from/to main memory to/from local buffers
- I/O is from the device to local buffer of controller
- Device controller informs CPU that it has finished its operation by causing an interrupt

Common Functions of Interrupts

- Interrupt transfers control to
 - ISR generally, through the interrupt vector
 - interrupt vector : addresses of all service routines
- Interrupt architecture must save
 - Address of the interrupted instruction
- A trap or exception
 - Software-generated interrupt caused either by an error or a user request
 - It do not go to Interrupt controller, but it handle on its own.. (Similar to: if Director get a problem he don't ask to PA but solve himself)
- An operating system is interrupt driven

Interrupt Handling

- OS preserves the state of the CPU
 - By storing registers and the program counter
- Determines which type of interrupt has occurred:
 - -polling
 - –vectored interrupt system
- Separate segments of code determine what action should be taken for each type of interrupt

I/O Structure

- Blocking I/O methods
- After I/O starts, control returns to user program only upon I/O completion
 - Wait instruction idles the CPU until the next interrupt
 - Wait loop (contention for memory access)
 - At most one I/O request is outstanding at a time, no simultaneous I/O processing

I/O Structure

- Non-Blocking I/O methods
- After I/O starts, control returns to user program without waiting for I/O completion
 - System call request to the OS to allow user to wait for I/O completion
 - Device-status table contains entry for each I/O device indicating its type, address, and state
 - OS indexes into I/O device table to determine device status and to modify table entry to include interrupt

Storage Definitions and Notation Review


- Bit : Basic unit of storage
- Byte 8 bits
 - Smallest convenient chunk of storage
- Notation
 - kilobyte, or KB, is 1,024 bytes ≈ 10^3 - megabyte, or MB, is 1,024² bytes ≈ 10^6 - gigabyte, or GB, is 1,024³ bytes ≈ 10^9 - terabyte, or TB, is 1,024⁴ bytes ≈ 10^{12} - petabyte, or PB, is 1,024⁵ bytes ≈ 10^{15}

Storage Structure

- Main memory only large storage media that the CPU can access directly
 - Random access, Typically volatile
- Secondary storage extension of main memory that provides large nonvolatile storage capacity
- Hard disks rigid metal or glass platters covered with magnetic recording material
 - Disk surface is logically divided into tracks, which are subdivided into sectors
 - The disk controller determines the logical interaction between the device and the computer
- Solid-state disks faster than hard disks, nonvolatile
 - Various technologies, Becoming more popular

Storage Hierarchy

- Storage systems organized in hierarchy
 - -Speed, Cost, Volatility
- Caching copying information into faster storage system; main memory can be viewed as a cache for secondary storage
 - Locality of Reference
 - Locality Principle (Spatial and Temporal Locality)
- Device Driver for each device controller to manage I/O
 - Provides uniform interface between controller and kernel




Caching

- Important principle, performed at many levels in a computer (in hardware, operating system, software)
- Information in use copied
 - From slower to faster storage temporarily
- Faster storage (cache) checked first to determine if information is there
 - If it is, information used directly from the cache (fast)
 - If not, data copied to cache and used there
- Cache smaller than storage being cached
 - Cache management important design problem
 - Cache size and replacement policy

Direct Memory Access Structure

- DMA
- Used for high-speed I/O devices able to transmit information at close to memory speeds
- Device controller transfers blocks of data from buffer storage directly to main memory without CPU intervention
 - Taxi Wala to handle all Pickup and Drop of Conference
- Only one interrupt is generated per block, rather than the one interrupt per byte



Computer-System Architecture

- Most systems use a general-purpose processor
 - Most systems have special-purpose processors as well
- Multiprocessors growing in use and importance
- Also known as parallel systems, tightly-coupled systems Advantages include:
 - Increased throughput, Economy of scale
 - Increased reliability graceful degradation or fault tolerance
- Asymmetric Multiprocessing each processor is assigned a specific task.
- Symmetric Multiprocessing each processor performs all tasks

