Table Of Contents

Table Of Contents	1
Fask: OpenBSD Display hostname	2
Fask: OpenBSD Chane Host Name	2

nixCraft: Linux Tips, Hacks, Tutorials, And Ideas In Blog Format http://www.cyberciti.biz/

Home > Faq > Openbsd

OpenBSD Change Hostname

Posted by Vivek Gite <vivek@nixcraft.com>

This entry is part 2 of 5 in the series OpenBSD Networking [1]

OpenBSD Networking [1]

- OpenBSD Set / Change Default Gateway [2]
- OpenBSD Change Hostname
- OpenBSD Change / Set IP Address For Network Interface [3]
- OpenBSD Restart Networking Service [4]
- Openbsd change, add or display default gateway [5]

Q. How do I change my hostname under OpenBSD operating system?



A. The hostname command displays the name of the current host. The superuser (root) can set the host name by editing a /etc/myname file. This is used at system boot time by netstart to initialize the hostname.

Task: OpenBSD Display hostname

Type the any one of the following command

```
# hostname
```

cat /etc/myname

Output:

openbsd.nixcraft.in

Task: OpenBSD Chane Host Name

Simply login as root and type the following command:

```
# echo "new-hostname.domain.com" > /etc/myname
# echo "server.nixcraft.in" > /etc/myname
# echo 'unixbox' > /etc/myname
```

Series Navigation

«OpenBSD Set / Change Default Gateway [2]OpenBSD Change / Set IP Address For Network Interface» [3]

4000+ howtos and counting! Want to read more Linux / UNIX howtos, tips and tricks? Subscribe to our <u>daily email</u> newsletter or <u>weekly newsletter</u> to make sure you don't miss a single tip/tricks. Alternatively, subscribe via <u>RSS/XML</u> feed.

Article printed from Frequently Asked Questions About Linux / UNIX: http://www.cyberciti.biz/faq/

URL to article: http://www.cyberciti.biz/faq/howto-openbsd-change-hostname/

URLs in this post:

- [1] OpenBSD Networking: http://www.cyberciti.biz/faq/series/openbsd-networking/
- [2] OpenBSD Set / Change Default Gateway: http://www.cyberciti.biz/faq/openbsd-ip-routing-configuration/

- [3] OpenBSD Change / Set IP Address For Network Interface: http://www.cyberciti.biz/faq/openbsd-tcpip-networking-configuration/
- [4] OpenBSD Restart Networking Service: http://www.cyberciti.biz/faq/openbsd-restart-network/
- [5] Openbsd change, add or display default gateway: http://www.cyberciti.biz/faq/openbsd-gateway-openbsd-routing-howto/
- [6] Image: http://www.cyberciti.biz/faq/faq/category/openbsd/

Copyright © 2006-2010 <u>nixCraft</u>. All rights reserved. This print / pdf version is for personal non-commercial use only. More details http://www.cyberciti.biz/tips/copyright.