Table Of Contents

Table Of Contents	1
nstall pftop	
Start pftop	2
Further readings:	

Install pftop 2/3

nixCraft: Linux Tips, Hacks, Tutorials, And Ideas In Blog Format http://www.cyberciti.biz/

Home > Faq > FreeBSD

BSD PF Firewall: Displays Active Packetfilter States And Rules

Posted by Vivek Gite <vivek@nixcraft.com>

Q. How do I view active connections with $\frac{PF \text{ firewall}}{PF \text{ firewall}}$ under FreeBSD / OpenBSD UNIX operating system?



A. You need to use pftop command which displays the active packetfilter states and rules, and periodically updates this information. It provides a "top" like view of the PF state table.

Install pftop

pftop can be installed from the FreeBSD / OpenBSD ports collection, or downloaded from the pftop website. Under FreeBSD type the following command to update ports and install the latest version:

```
# portsnap fetch update
# cd /usr/ports/sysutils/pftop
```

make install clean

Start pftop

pftop displays source and destination IP addresses, TCP and UDP port numbers, packets and bytes transmitted, the age of a connection, and the time left until a connection will be removed from the state table:

```
# pftop
```

Sample output:

```
PR D SRC DEST STATE AGE EXP PKTS BYTES dept 1 213 ::35450 200.43.78.162:53 2:2 40 20 4 558 dept 1 213 ::35450 200.43.78.162:53 2:2 40 20 4 558 dept 1 33. :25006 200.43.78.162:53 1:2 37 0 2 256 dept 1 200 ::3 200.43.78.162:53 1:2 37 0 2 256 dept 1 200 ::3 200.43.78.162:53 1:2 37 0 2 250 dept 1 200 ::3 200.43.78.162:53 1:2 37 0 2 250 dept 1 262 ::3 200.43.78.162:53 1:2 37 0 2 250 dept 1 263 ::3 200.43.78.162:53 1:2 35 0 2 200 dept 1 162 ::178:17886 200.43.78.162:53 1:2 35 0 2 250 dept 1 163 ::3 3119 200.43.78.162:53 1:2 34 0 2 250 dept 1 23. :3 3119 200.43.78.162:53 1:2 32 0 2 250 dept 1 30. :256602 200.43.78.162:53 1:2 32 0 2 250 dept 1 90. ::58640 200.43.78.162:53 1:2 32 0 2 260 dept 1 90. ::58640 200.43.78.162:53 1:2 32 0 2 260 dept 1 90. ::25602 200.43.78.162:53 1:2 32 0 2 260 dept 1 90. ::55241 200.43.78.162:53 1:2 32 0 2 260 dept 1 90. ::55241 200.43.78.162:53 1:2 32 0 2 260 dept 1 90. ::55241 200.43.78.162:53 1:2 32 0 2 260 dept 1 193 1:553 200.43.78.162:53 1:2 32 0 2 260 dept 1 193 1:553 200.43.78.162:53 1:2 32 0 2 260 dept 1 193 1:553 200.43.78.162:53 1:2 32 0 2 260 dept 1 195 1:700.43.78.162:53 1:2 32 0 2 260 dept 1 195 1:700.43.78.162:53 1:2 32 0 2 260 dept 1 195 1:700.43.78.162:53 1:2 32 0 2 260 dept 1 195 1:700.43.78.162:53 1:2 32 0 2 260 dept 1 195 1:700.43.78.162:53 1:2 32 0 2 260 dept 1 100. 1:26602 200.43.78.162:53 1:2 32 0 2 260 dept 1 100. 1:55340 200.43.78.162:53 1:2 32 0 2 260 dept 1 100 1:5540 200.43.78.162:53 1:2 32 0 2 260 dept 1 100 1:26602 200.43.78.162:53 1:2 32 0 2 260 dept 1 200 1:48990 200.43.78.162:53 1:2 37 0 2 260 dept 1 200 1:48950 200.43.78.162:53 1:2 37 0 2 260 dept 1 200 1:48950 200.43.78.162:53 1:2 37 7 2 200 dept 1 200 1:266790 200.43.78.162:53 1:2 23 7 2 200 dept 1 200 1:266790 200.43.78.162:53 1:2 23 7 2 200 dept 1 200 1:266790 200.43.78.162:53 1:2 23 7 2 200 dept 1 200 1:266790 200.43.78.162:53 1:2 23 7 2 200 dept 1 200 1:266790 200.43.78.162:53 1:2 23 7 2 200 dept 1 200 1:266790 200.43.78.162:53 1:2 23 7 2 200 dept 1 200 1:26690 200.43.78.162:53 1:2 23 7 2 200 dept 1 200
```

Fig.01: pftop in action (click to enlarge)

To exit press **q**. Following commands are currently recognized:

С	Enable disable state caching (enabled by default).
f	Set the state filter expression.
h,?	Display a summary of the commands (help screen).
n	Set number of lines to display.
О	Select next sorting Order.
р	Pause/resume display updates.
q	Quit pftop.
r	Reverse current sorting order.
s	Set display update interval in Seconds.
v	Select next View.

Install pftop 3/3

0-7	Select one of the views directly.
Cursor	Scroll display (up/down), and switch views (left/right). Most of the emacs/mg motion keys work as well.
SPACE	Update display immediately.
CTRL-L	Refresh display.
CTRL-G	Clear command entry line.

Further readings:

• man page pftop, pf and pfctl

4000+ howtos and counting! Want to read more Linux / UNIX howtos, tips and tricks? Subscribe to our <u>daily email</u> newsletter or <u>weekly newsletter</u> to make sure you don't miss a single tip/tricks. Alternatively, subscribe via <u>RSS/XML</u> feed.

Article printed from Frequently Asked Questions About Linux / UNIX: http://www.cyberciti.biz/faq/

URL to article: http://www.cyberciti.biz/faq/bsd-pf-viewing-active-connections-with-pftop/

URLs in this post:

- [1] Image: http://www.cyberciti.biz/faq/category/openbsd/
- [2] PF firewall: http://bash.cyberciti.biz/firewall/pf-firewall-script/
- [3] Image: http://www.cyberciti.biz/faq/category/freebsd/
- [4] Image: http://www.cyberciti.biz/faq/wp-content/uploads/2008/09/pftop.png

Copyright © 2006-2010 <u>nixCraft</u>. All rights reserved. This print / pdf version is for personal non-commercial use only. More details http://www.cyberciti.biz/tips/copyright.