# **Table Of Contents**

Table Of Contents	1
Task: Find out device name	
Task: Formatting a cd rw on Linux	2
Task: Formatting a dvd rw on Linux	
Task: Using GUI tool - k3b	3
See also:	

nixCraft: Linux Tips, Hacks, Tutorials, And Ideas In Blog Format <a href="http://www.cyberciti.biz/">http://www.cyberciti.biz/</a>

#### Home > Faq > CentOS

## Linux Formatting a CDRW / DVD Media (blank media) Commands

Posted by Vivek Gite <vivek@nixcraft.com>

Q. How do I blank / format my CDRW / DVD media under Linux using a shell prompt?

A. You can use wodim (cdrecord) to record data or audio Compact Discs on an Orange Book CD-Recorder or to write DVD media on a DVD-Recorder



### Task: Find out device name

Find find out your CDRW drive name by entering following command:

```
$ cdrecord -scanbus
```

```
or
$ wodim -scanbus
```

#### Output:

```
scsibus1:
                100) 'TSSTcorp' 'CD/DVDW SH-S182D' 'SB04' Removable CD-ROM
        1,0,0
        1,1,0
                101) *
        1,2,0
                102) *
        1,3,0
                103) *
        1,4,0
                104) *
        1,5,0
                105) *
        1,6,0
                106) *
        1,7,0
                107) *
```

Note that 1,0,0 is the device name you need to use.

#### Task: Formatting a cd rw on Linux

Insert CD and enter following command to format CDRW (note for formatting DVD use dvd+rw-format command, see below):

```
$ cdrecord blank=fast dev=1,0,0
```

OR

```
$ sudo cdrecord blank=fast dev=1,0,0
```

Above command will blank a CD-RW and exit or blank a CD-RW before writing. The blanking type is fast, but it may be one of the following:

- all : Blank the entire disk. This may take a long time.
- fast: Minimally blank the disk. This results in erasing the PMA, the TOC and the pregap.
- track Blank a track.
- unreserve Unreserve a reserved track.
- trtail Blank the tail of a track.
- unclose Unclose last session.
- session Blank the last session.

## Task: Formatting a dvd rw on Linux

Use <u>dvd+rw-format command</u> [2] to formats dvd disk in the specified dvd drive such as /dev/dvd:

\$ dvd+rw-format -force /dev/dvd

OR

\$ sudo dvd+rw-format -force /dev/dvd

## Task: Using GUI tool - k3b

k3b is a CD/DVD burning tool. It can format CD/DVD RW. First install k3b:

\$ sudo apt-get install k3b

Start k3b from menus or just type

\$ k3b &

Now click on Tools menu > Erase CDRW to format CDRW OR

Now click on Tools menu > Format DVD to format DVD



#### See also:

Howto: Linux write bur data to DVD or DVD/RW [2]

Updated for accuracy!

4000+ howtos and counting! Want to read more Linux / UNIX howtos, tips and tricks? Subscribe to our <u>daily email</u> newsletter or <u>weekly newsletter</u> to make sure you don't miss a single tip/tricks. Alternatively, subscribe via <u>RSS/XML</u> feed.

Article printed from Frequently Asked Questions About Linux / UNIX: http://www.cyberciti.biz/faq/

URL to article: http://www.cyberciti.biz/faq/howto-linux-format-cdrw-dvdrw/

URLs in this post:

- [1] Image: http://www.cyberciti.biz/faq/faq/category/linux/
- [2] dvd+rw-format command: http://www.cyberciti.biz/tips/howto-linux-write-burn-data-to-dvd-or-dvdrw.html
- [3] Image: http://www.cyberciti.biz/faq/howto-linux-format-cdrw-dvdrw/linux-blanking-formatting-cdrw-cd-dvd-media-using-k3b/

details http://www.cyberciti.biz/tips/copyright.