Table Of Contents 1/3

Table Of Contents

Table Of Contents	1
Restart Dovecot IMAP mail server	2
A Note About Debian / Ubuntu Linux User	2

nixCraft: Linux Tips, Hacks, Tutorials, And Ideas In Blog Format http://www.cyberciti.biz/

Home > Faq > CentOS

Linux Restart IMAP Services (dovecot IMAP server)

Posted by Vivek Gite <vivek@nixcraft.com>

This entry is part 1 of 2 in the series Linux Service Management [1]

Linux Service Management [1]

- Linux Restart IMAP Services (dovecot IMAP server)
- How do I find out what ports are listening/open on my Linux / FreeBSD server? [2]

Q. How do I restart dovecot IMAP4 / IMAP (Internet Message Access Protocol) under RHEL / CentOS / Fedora / Debian / Ubutnu Linux?

A. Internet Message Access Protocol is a standard client / server protocol for accessing e-mail from your local server. It will not just retrieve email but view it and manipulate it on the server itself. IMAP4 clients can create, rename, and/or delete mailboxes (usually presented to the user as folders) on the server, and move messages between mailboxes. Multiple mailbox support also allows servers to provide access to shared and public folders.



[3]

IMAM server port number: 143

Under Linux you can diffrent IMAP server can be installed.

Restart Dovecot IMAP mail server

Type the following command to start / stop and restart server under RHEL / CentOS / Fedora Linux:

```
# service dovecot start
# service dovecot stop
# service dovecot restart
```

Automatically reload sever next boot, enter:

```
# chkconfig dovecot on
```

To turn off auto loading on next boot, enter:

```
# chkconfig dovecot off
```

A Note About Debian / Ubuntu Linux User

Type the following command to start / stop and restart server under Debian / Ubuntu Linux:

```
# /etc/init.d/dovecot start
# /etc/init.d/dovecot stop
# /etc/init.d/dovecot restart
```

Use a text-based application called sysvconfig that allows you to configure which services are started at boot time for each runlevel including dovecot under Debian / Ubuntu Linux:

```
# sysvconfig
```

Series Navigation

4000+ howtos and counting! Want to read more Linux / UNIX howtos, tips and tricks? Subscribe to our <u>daily email</u> newsletter or <u>weekly newsletter</u> to make sure

you don't miss a single tip/tricks. Alternatively, subscribe via RSS/XML feed.

Article printed from Frequently Asked Questions About Linux / UNIX: http://www.cyberciti.biz/faq/

URL to article: http://www.cyberciti.biz/faq/linux-restart-imap-services-dovecot-imap-server/

URLs in this post:

- [1] Linux Service Management: http://www.cyberciti.biz/faq/series/services-management/
- [2] How do I find out what ports are listening/open on my Linux / FreeBSD server?: http://www.cyberciti.biz/faq/how-do-i-find-out-what-ports-are-listeningopen-on-my-linuxfreebsd-server/
- [3] Image: http://www.cyberciti.biz/faq/faq/category/linux/

Copyright © 2006-2010 <u>nixCraft</u>. All rights reserved. This print / pdf version is for personal non-commercial use only. More details http://www.cyberciti.biz/tips/copyright.